
ScummVM Documentation

CadiH

Nov 30, 2020

The basics

1	Understanding the interface	4
1.1	The Launcher	4
1.2	The Global Main Menu	7
2	Handling game files	10
2.1	Multi-disc games	11
2.2	CD audio	11
2.3	Macintosh games	11
3	Adding and playing a game	13
3.1	Where to get the games	13
3.2	Adding games to the Launcher	13
3.3	A note about copyright	21
4	Saving and loading a game	22
4.1	Saving a game	22
4.2	Location of saved game files	27
4.3	Loading a game	27
5	Keyboard shortcuts	30
6	Changing settings	31
6.1	From the Launcher	31
6.2	In the configuration file	31
7	Connecting a cloud service	32
8	Using the local web server	37
9	AmigaOS 4	42
9.1	What you'll need	42
9.2	Installing ScummVM	42
9.3	Transferring game files	42
9.4	Controls	44
9.5	Paths	44
9.6	Settings	44
9.7	Known issues	44
10	Android	45

10.1	What you'll need	45
10.2	Installing ScummVM	45
10.3	Transferring game files	46
10.4	Controls	47
10.5	Paths	48
10.6	Known issues	48
11	Atari/FreeMiNT	49
11.1	What you'll need	49
11.2	Installing ScummVM	49
11.3	Transferring game files	50
11.4	Controls	50
11.5	Paths	50
11.6	Settings	50
11.7	Known issues	51
12	iOS	52
12.1	Installing ScummVM	52
12.2	Transferring game files	55
12.3	Controls	56
12.4	Paths	57
13	Nintendo 3DS	58
13.1	What you'll need	58
13.2	Installing ScummVM	58
13.3	Transferring game files	59
13.4	Controls	59
13.5	Paths	60
13.6	Settings	60
13.7	Known issues	62
14	Nintendo Switch	63
14.1	What you'll need	63
14.2	Installing ScummVM	63
14.3	Transferring game files	63
14.4	Controls	64
14.5	Paths	66
14.6	Settings	66
15	PlayStation 3	68
15.1	What you'll need	68
15.2	Installing ScummVM	68
15.3	Transferring game files	68
15.4	Controls	69
15.5	Paths	69
15.6	Settings	69
16	PlayStation Portable	71
16.1	What you'll need	71

16.2	Installing ScummVM	71
16.3	Transferring game files	72
16.4	Controls	72
16.5	Settings	74
16.6	Paths	74
16.7	Known issues	74
17	PlayStation Vita	75
17.1	What you'll need	75
17.2	Installing ScummVM	75
17.3	Transferring game files	75
17.4	Controls	76
17.5	Paths	78
17.6	Settings	79
17.7	Known Issues	79
18	RISC OS	80
18.1	What you'll need	80
18.2	Installing ScummVM	80
18.3	Transferring game files	80
18.4	Controls	81
18.5	Paths	81
18.6	Settings	81
18.7	Known issues	81
19	Sega Dreamcast	82
19.1	What you'll need	82
19.2	Running ScummVM	82
19.3	Transferring game files	84
19.4	Controls	85
19.5	Paths	85
19.6	Settings	86
19.7	Known issues	86
20	Game	87
21	Engine	89
21.1	ADL	89
21.2	AGI	91
21.3	BLADERUNNER	91
21.4	CGE	92
21.5	CINE	92
21.6	DRASCULA	92
21.7	DREAMWEB	92
21.8	HDB	93
21.9	HOPKINS	93
21.10	KYRA	93
21.11	LURE	94

21.12	MADS	94
21.13	NEVERHOOD	94
21.14	QUEEN	95
21.15	SCI	95
21.16	SCUMM	96
21.17	SHERLOCK	96
21.18	SKY	97
21.19	SUPERNOVA	97
21.20	TOLTECS	97
21.21	WINTERMUTE	97
21.22	XEEN	98
22	Graphics	99
23	Control	102
24	Keymaps	104
24.1	Global settings	104
24.2	Game settings	108
25	Audio	109
25.1	The Audio tab	109
25.2	The Volume tab	112
25.3	The MIDI tab	113
25.4	The MT-32 tab	117
26	Paths	119
27	Miscellaneous	121
28	Cloud	123
29	LAN	125
30	Accessibility	127
31	Command line interface	129
31.1	Usage	129
31.2	Options	130
32	Configuration file	133
32.1	Location	133
32.2	Using the configuration file	134
32.3	Configuration keys	135
33	Understanding the audio settings	145
33.1	How do the audio settings work together?	145
33.2	The evolution of PC audio	145
33.3	What is MIDI?	146
33.4	What is AdLib?	149

33.5	Digital Sound effects	150
33.6	Sample output rate	150
33.7	Audio buffer size	150
34	Understanding the graphics settings	151
34.1	How do the graphics settings work together?	151
34.2	Graphics modes	151
34.3	Aspect ratio correction	155
34.4	Stretch modes	156
34.5	Render mode	158
34.6	Filter graphics	158
35	Report a bug	162
35.1	The ScummVM log file	162
36	Contact us	164
37	Frequently Asked Questions	165
37.1	General	166
37.2	Troubleshooting	169
38	Version 2.2.0 - “Interactive Fantasy”	172
38.1	New games	172
38.2	New ports	173
38.3	Engines	173
38.4	Ports	177
39	Welcome to ScummVM!	179
39.1	Start here!	179
39.2	Advanced topics	180
39.3	Getting help	181
39.4	What’s changed since I was last here?	181
39.5	The ScummVM Project	181

This page explains how to install ScummVM on a computer. For all other platforms, see the relevant *platform guide*.

Windows

There are two ways to install ScummVM on Windows: use the installer, or install manually.

Installing ScummVM using the installer

Download the Windows installer for your operating system from the [ScummVM downloads page](#), and double click the downloaded file. The installer guides you through the install process, and adds a shortcut to the Start Menu. There is also an option to add a shortcut to the desktop.

To run ScummVM, either navigate to desktop and double click the ScummVM shortcut, or go to **Start > All Apps > ScummVM**. For Windows XP, go to **Start > All Apps > ScummVM**.

Installing ScummVM manually

Download the Windows zip file for your operating system (32bit or 64bit). To extract the files, right-click the folder and select **Extract All**.

To run ScummVM from the extracted folder, find the `scummvm.exe` file and double click it.

macOS

Installing ScummVM using the disk image

Download the recommended disk image file from the [ScummVM downloads page](#). After the download has completed, double click the file to mount the disk image file. A window containing the ScummVM icon opens. Drag this icon into your Applications folder to install ScummVM.

To run ScummVM, click on the icon in the Applications folder.

Note: macOS includes technology called Gatekeeper, which checks to ensure only trusted software is run on your Mac. ScummVM is not available from the App Store, so follow the steps on this [Apple support page](#) to allow ScummVM to run.

Linux

There are multiple ways to install ScummVM on Linux: use the Snap Store, Flathub or the software repository, or manually install the release binary.

Installing ScummVM using the Snap Store

A Snap is an app that is bundled with its dependencies, which makes the install on any Linux operating system very easy. Snap comes pre-installed on Debian and Ubuntu-based distributions, but can be installed on any Linux distribution by following the instructions on the [Snapcraft website](#).

The ScummVM Snap comes with a selection of freeware games and demos pre-loaded.

Enter the following on the command line to install the ScummVM Snap:

```
sudo snap install scummvm
```

To run ScummVM, enter `scummvm` on the command line, or launch ScummVM through the desktop interface by clicking **Menu > Games > ScummVM**.

Installing ScummVM using Flathub

Flathub is another way to install apps for Linux, by using Flatpak. Flatpak comes standard with Fedora-based distributions, but can be installed on any Linux operating system. The [Flathub website](#) has excellent install instructions.

When Flatpak is installed, enter the following on the command line to install ScummVM:

```
flatpak install flathub org.scummvm.ScummVM
```

Some distributions have the option to install Flatpaks through the graphical desktop interface. Navigate to the [ScummVM Flatpak page](#), click the **INSTALL** button and then follow the install process.

To run ScummVM, enter the following on the command line:

```
flatpak run org.scummvm.ScummVM
```

To pass *Command line arguments*, add them after the Flatpak run command.

Note: The Flatpak version of ScummVM is sandboxed, meaning that any games need to be copied into the Documents folder to be accessible by ScummVM.

Installing ScummVM using the software repository

ScummVM is found in the software repositories of many Linux distributions.

Caution: The repositories might not contain the most up-to-date version of ScummVM.

To run ScummVM, enter `scummvm` on the command line, or launch ScummVM through the desktop interface by clicking **Menu > Games > ScummVM**.

Installing ScummVM using the release binaries

Binary packages are only released for Debian and Ubuntu. On the [ScummVM downloads page](#), find and download the ScummVM package that corresponds to your operating system and architecture. To install a DEB package, either double click on the downloaded DEB file to use the graphical installer, or, if that's not available, use the command line.

```
sudo apt install /path/to/downloaded/file.deb
```

Replace `/path/to/downloaded/file.deb` with the actual path to the downloaded DEB package. The APT software manager handles the installation.

To run ScummVM, enter `scummvm` on the command line, or launch ScummVM through the desktop interface by clicking **Menu > Games > ScummVM**.

Chapter 1

Understanding the interface

1.1 The Launcher

The main ScummVM window is called the Launcher. The Launcher opens whenever you start ScummVM, unless you launch a game directly from the command line.

1.1.1 The games list

The pane on the left is the games list, which lists all the games that have been added to ScummVM. The games list usually offers some additional information about each game, such as original platform and language. To highlight any game on the list, type the first letter(s) of its title, or click on it.

1.1.2 The search box

The search box lets you filter the games list. It is located at the top of the page next to the magnifying glass icon. The filter is applied as you type, and is not case sensitive. To clear the filter, click X.

There are many ways to filter games. For example, you can type “Monkey Island” to locate all “Monkey Island” games on the list, or you can type “German” to find German games.

1.1.3 The buttons

To the right of the games list there are a number of buttons. Their functions are as follows:




Fig. 1: The Launcher, with labels for each GUI element.

Start

Launches the highlighted game.

Load

Opens the load game window, from which you can go to a saved game without having to start the game first.

See the *[Saving and loading a game](#)* page.

Add Game

Opens a file browser. To add a game, select a folder containing game files.

See the *[Adding and playing a game](#)* page.

Edit Game

Opens the game settings window. This window also opens whenever a game is added to the games list in the Launcher.

Use this window to configure settings specific to a game. These settings override the global settings. For more information, see the *[Changing settings](#)* page.

Remove Game

Removes the highlighted game from the list. This does not remove any saved games, so if you add a game to the games list again, you are able to resume where you left off.

Options

Opens the global settings window. Use this window to define global game settings, as well as change a number of the ScummVM Launcher settings. For more information, see the *[Changing settings](#)* page.

About

Shows credits and miscellaneous information about ScummVM.

Quit

Closes the Launcher and quits the ScummVM application.

1.2 The Global Main Menu

You can access the ScummVM Global Main Menu, also known as the GMM, while you are playing a game. To open the GMM, press Ctrl+F5 (Ctrl+fn+F5 on a Mac).




Fig. 2: The Global Main Menu, or GMM.

1.2.1 The buttons

In the Global Main Menu there are a number of buttons. Their functions are as follows:

Resume

Closes the GMM and resumes the game.

Load

Opens the load game window. From here, you can load a saved game.

Save

Opens the save game window. From here, you can save a game.

Options

Opens a dialog which provides some gameplay options, such as sound volume, subtitle and keymap settings.

About

Displays the ScummVM **About** dialog. This is also available from the Launcher.

Help

Displays a list of keyboard shortcuts for the game.

Return to Launcher

Quits the game and returns to the Launcher.

Note: This is not available for all games.

Quit

Quits the game and ScummVM, and returns to the operating system. Any unsaved game progress is lost.

Chapter 2

Handling game files

ScummVM needs access to the data files for each game. A comprehensive list of required data files for each game is found on the [ScummVM Wiki Datafiles](#) page. ScummVM can run the game data files from any directory it has access to, including external media.

Note: For ease of use, you can create a dedicated games folder into which folder containing game files can be copied. The resulting directory structure will look somewhat like this:

```
ScummVM Games
|-- Day of the Tentacle
|   |-- MONSTER.SOU
|   |-- TENTACLE.000
|   `-- TENTACLE.001
`-- Flight of the Amazon Queen
    |-- QUEEN.1
    `-- queen.tbl
```

For games on floppies or CDs, if the data files are accessible, the external media can be accessed directly by ScummVM. Alternatively, copy the game files to a folder as described above. If the data files are not accessible, run the installer on the platform the game was designed for, to extract the game files.

For games downloaded from digital distributors or from various [freeware sources](#) run the installer to extract the data files, or if the data files are supplied as a zip file, extract the files.

For macOS or Linux users without access to a Windows machine, you can get the data files from games that only have Windows installers. Use [Wine](#) to run the Windows installer. Alternatively, for GOG.com games, use [innoextract](#) to unpack game files from the installer without actually running it.

Tip: Use ScummVM's Cloud functionality to share game files and automatically back up and sync your saved game states. For detailed instructions see the [Connecting a cloud service](#) guide. For devices on the same local network, ScummVM can also run a web server to allow hassle-free transfer of files. For detailed instructions, see the [Using the local web server](#) guide. This is a good

option if you do not wish to connect a Cloud service.

2.1 Multi-disc games

ScummVM needs access to all the data files, so it will not be able to run directly from a CD if the game has multiple discs. To add a multi-CD game, copy the required data files from the CD to a folder on your hard drive. For a comprehensive list of required files, see the [ScummVM Wiki Datafiles](#) page.

As a general guideline, where there are duplicate, identical files (same name, same file size) on more than one disc, only one copy of the file is required. Where there are files that have the same name but are different on each disc, rename them. For example, where there is a `music.clu` on two discs, rename the file on the first disc to `music1.clu` and the file on the second disc to `music2.clu`.

2.2 CD audio

In most cases, ScummVM can use CD audio directly from the game CD. If you don't always want to insert the game CD to use the CD audio, you can extract the audio tracks from the CD and save them locally:

1. Extract the CD audio tracks in WAV or AIFF format.
2. Convert the tracks to either MP3, FLAC or OGG file formats.
3. Place the converted audio files in the same folder that contains the other game datafiles.

Tip: [fre:ac](#) is a multi-platform, open-source software, with the ability to both rip CDs and convert audio between MP3, OGG, FLAC and WAV file formats.

2.3 Macintosh games

All LucasArts SCUMM games also exist in versions for the Macintosh. Most of the newer games shipped with only a single data file; ScummVM can use this file like it does any other data file. Some discs shipped with hidden files. To view hidden files in macOS, press `Cmd+Shift+.` in a Finder window.

Mac uses a different file system to other systems (HFS+), so to access the CD or floppy disc on a Windows or Linux system you need additional software to view and copy the files.

For Windows, [HFS Explorer](#) is a basic and free option, which gives you read-only access to HFS drives. Use the installer rather than the zip file, to ensure it is installed correctly.

For Linux, `hfsplus` gives you read-only access to HFS drives. To use `hfsplus`, use the command line:

1. Install hfsplus using the software manager. On Debian-based distributions, use `sudo apt install hfsplus`.
2. Find the game disc by running `sudo fdisk -l` and finding the one with type Apple HFS/HFS+. In this example, this is `/dev/fd0`.
3. Create a mount point, for example: `sudo mkdir /media/macgamedrive`
4. Mount the device to that mount point: `sudo mount -t hfsplus /dev/fd0 /media/macgamedrive`
5. Access the device at `/media/macgamedrive`.

Chapter 3

Adding and playing a game

3.1 Where to get the games

One of the most frequently asked questions is, “Where do I get the games?!?”. If you still have your old floppy discs or CDs lying around, and have a way to read them, then you can use the game files from those original discs.

If you haven’t had a floppy disc or even a CD in your possession for a while, there is a [ScummVM wiki page](#) dedicated to helping you find some games to play.

Tip: ScummVM has an affiliate referrer programme with GOG.com, so if you are going to buy a game, please use this [GOG.com](#) link to help the project!

Make sure to check out the [compatibility list](#) on the ScummVM website, and the [Supported Games page](#) and [Platform Overview page](#) on the ScummVM wiki before you buy a game, to ensure it can run with ScummVM.


3.2 Adding games to the Launcher

The following steps explain how to add a game to ScummVM, and assume you have access to the data files for each game. If you’re not sure how to access the game data files, see the [Handling game files](#) page.


1. Run ScummVM to open *the Launcher*.
2. In the Launcher window, click **Add Game**. This opens a file browser; either the system file browser or the ScummVM file browser.



To add multiple games at once, click the expander arrow next to **Add Game**, and select **Mass Add**.





3. Use the file browser to locate the folder containing the game data files. For the ScummVM file browser: Double click on a folder to open it, and use **Go up** to go back up one level. Highlight the folder by clicking on it, and then click **Choose**



Note: The **Use Native file browser** option in the [Misc](#) tab of the global settings controls whether ScummVM uses the system file browser, or its own file browser.

If you are using **Mass Add**, select **Yes** to run the mass game detector. A dialog opens to advise which games were added to the games list.






Sometimes, ScummVM detects multiple versions of a single game. In this case, highlight the correct version and click **Choose** to continue.

Caution: If you are using **Mass Add**, ScummVM adds all versions of a game.


If you are adding an unknown version of a game, ScummVM is not able to add the game to the games list. An error message appears to warn you that the game has not been added.

4. The **Edit Game** dialog opens to allow configuration of various settings for the game. These can be reconfigured at any time, but for now everything should be OK at the default settings. Any settings changed here override the global settings. Click **Ok**.



Note: The **Edit Game** dialog does not open when **Mass Add** is used.

6. Games are now ready to play! To play, highlight a game in the games list and click **Start**, or double-click the game in the games list.



Games can also be launched directly from the command line. For more information, see the [Command line options](#) page.

3.3 A note about copyright

ScummVM has a strict anti-piracy stance and the team will not tolerate discussions around pirated games in any part of the project, including on the Forum or on Discord.

3.3.1 Copy protection screen

There are cases where the game companies themselves bundled ‘cracked’ executables with their games. In these cases the data files still contain the copy protection scripts, but the interpreter bypasses them; similar to what an illegally cracked version might do, only that here the producer of the game did it. There is no way for ScummVM to tell the difference between legitimate and pirated data files, so for the games where a cracked version of the original interpreter was sold at some point, ScummVM has to bypass the copy protection.

In some cases ScummVM still shows the copy protection screen. Enter any answer; chances are that it will work.

Chapter 4

Saving and loading a game

This page explains how to save and load a game from the Global Main Menu, or load a game directly from the Launcher.

Note: Some games use their own load or save entry points within the game, or use their own menu instead of the GMM.

4.1 Saving a game

When you're playing a game and you're ready to save, press Ctrl+F5 (Ctrl+fn+F5 on a Mac) to access the Global Main Menu. Select **Save**.

There are two views: list view and tile view. Click the list and tile icons at the bottom left of the window to toggle between the two.

In tile view, click on the **New Save** tile. Enter a description for the game, then click **OK**.

In list view, click on a slot to save the game to that slot. Enter a description for the game, then click **Save**.

4.1.1 Autosave

ScummVM automatically saves your game every 5 minutes. The *autosave period* can be changed in the Misc settings tab, or in the *configuration file*.



Fig. 1: The Global Main Menu (GMM).



Fig. 2: Saving a game, tile view.



Fig. 3: Save game decription, tile view.




Fig. 4: Saving a game, list view.

4.2 Location of saved game files

The save directory can be changed with the `savepath` setting in the [Paths tab](#). It can also be changed in the [configuration file](#).

Default saved game paths are shown below.

Windows

Windows NT4

C:\WINDOWS\Profiles\username\Application Data\ScummVM\Saved games\

Windows 2000/XP

\Documents and Settings\username\Application Data\ScummVM\Saved games\

Window Vista/7/8/10

%APPDATA%\ScummVM\Saved games

macOS

~/Documents/ScummVM Savegames/

Linux/Unix

ScummVM follows the XDG Base Directory Specification, so by default the saved games can be found at `~/.local/share/scummvm/saves/`, but this location might vary depending on the value of the `XDG_DATA_HOME` environment variable.

`.local` is a hidden directory. To view it use `ls -a` on the command line.

If ScummVM was installed using Snap, the saves can be found at `~/snap/scummvm/current/.local/share/scummvm/saves/`

4.3 Loading a game

If you want to load your saved game without having to start the game first, select the **Load** button directly from the Launcher. To load a saved game while you're playing a game, press `Ctrl+F5` (`Ctrl+fn+F5` on a Mac) to access the Global Main Menu, then select **Load**.

There are two views: list view and tile view. Click the list and tile icons at the bottom left of the window to toggle between the two.

In list view, the pane on the left shows a list of your saved games. Click on a saved game to highlight it. In the pane on the right you can see timestamps, screenshots and playtime for that saved game.

Once you have highlighted the game you want to play, click **Load**.

To delete a saved game, highlight the saved game and click **Delete**.




Fig. 5: Loading a game, list view.

In tile view, each tile shows a screenshot of the saved state, as well as a description and a save slot number. Click on the tile to load that saved game.



Fig. 6: Loading a game, tile view.

Chapter 5

Keyboard shortcuts

ScummVM supports various in-game keyboard and mouse shortcuts, and since version 2.2.0 these can be manually configured in the [Keymaps tab](#), or in the [configuration file](#).

For game-specific controls, see the [wiki entry](#) for the game you are playing.

Default shortcuts are shown in the table.

Shortcut	Description
Ctrl+F5	Displays the Global Main Menu
Cmd+q	Quit (macOS)
Ctrl+q	Quit (Linux/Unix)
Alt+F4	Quit (Windows)
Ctrl+z	Quit (other platforms)
Ctrl+u	Mutes all sounds
Ctrl+m	Toggles mouse capture
Ctrl+Alt+ 1-8	Switches between graphics filters
Ctrl+Alt and + or -	Increases/decreases the scale factor
Ctrl+Alt+a	Toggles aspect ratio correction on/off
Ctrl+Alt+f	Toggles between nearest neighbor and bilinear interpolation (graphics filtering on/off)
Ctrl+Alt+s	Cycles through stretch modes
Alt+Enter	Toggles full screen/windowed mode
Alt+s	Takes a screenshot
Ctrl+F7	Opens virtual keyboard (if enabled). This can also be opened with a long press of the middle mouse button or wheel.

Chapter 6

Changing settings

6.1 From the Launcher

The settings are arranged by subject, on different tabs:

Game tab | *Engine tab* | *Graphics tab* | *Control tab* | *Keymaps tab* | *Audio tab* | *Volume tab* | *Midi tab* | *MT-32 tab* | *Paths tab* | *Misc tab* | *Cloud tab* | *LAN tab* | *Accessibility tab*

To change a setting globally, so that it affects all games, select **Options** and then select the tab containing the setting you would like to change.

To change a setting for just one game, highlight the game in the games list, then select **Edit Game** and select the tab containing the setting you would like to change. To make the game use the settings on that tab instead of the global settings tab, tick **Override global settings**.

Not all settings are available for all games; for example, where there is no MIDI soundtrack for a game, there will be no MIDI or MT-32 tabs.

6.2 In the configuration file

See the *configuration file* page for more information on how to do this. Configuration keys are listed in the Settings pages, after the description of each setting, in italics.

Chapter 7

Connecting a cloud service

Connecting ScummVM to a cloud storage service provides an easy way of sharing game files and saved games between multiple devices. ScummVM currently supports Dropbox, OneDrive, Google Drive and Box, although only one service can be connected at any one time.

Note: Cloud functionality is not supported on all platforms.

This guide explains how to connect a cloud service to ScummVM.

From the Launcher, select **Options**, click the > scroll arrow until the Cloud tab is visible, and then select the **Cloud** tab.

Select your preferred cloud storage service from the **Active storage** dropdown.

Click on the link shown at **1.**, and sign in to your cloud storage account. A 6-digit code is displayed after you sign in.

Warning: Do not share this 6-digit code with anyone before you connect your cloud storage account.

For devices without a web browser, navigate to the following ScummVM links on a computer or any other device with a web browser:

[Dropbox](#) | [OneDrive](#) | [Google Drive](#) | [Box](#)

Copy the 6-digit code, click into the empty field next to **Paste**, and then click **Paste**. Alternatively, for devices without a web browser, manually enter the 6-digit code.

Click **3. Connect**. After the next page loads, click **Enable storage**.

Saved games sync automatically on launch, when a game is saved, and when a saved game is loaded. Select **Sync now** to manually sync.

To download game files from your cloud ScummVM folder, click **Download game files**.







To change to a different cloud account, or to disconnect your cloud account from ScummVM, click **Disconnect**.

Chapter 8

Using the local web server

ScummVM can run a local web server (LAN), to simplify the transfer of game files, saved games and configuration files between devices on the same network. This is a good option if you do not want to use the Cloud, or if ScummVM for your platform does not have cloud functionality.

Note: LAN functionality is not supported on all platforms.

This guide explains how to set up and run a local web server.

From the Launcher, select **Options**, click the > scroll arrow until the LAN tab is visible, and then select the **LAN** tab.

Click **Run server** to start the server.

To access the server, type the URL shown into the address bar of any web browser:

To download a file, click on the file to open the system download dialog.

To create a new directory, click **Create Directory**.

To upload files, click **Upload Files** and select files from the system file browser.

To change which files are accessible on the web server, set the **/root/ Path** to the directory containing the files you wish to access. You can access anything inside that directory, but you cannot access its parent directory. On some platforms ScummVM automatically sets the **/root/ Path**, but on some other platforms you need to configure this manually before running the web server for the first time.

To stop the web server, click **Stop server** to stop the server, or click **Ok** to close the settings dialog.



Fig. 1: The LAN tab, with the server running.




Fig. 2: The server's browser interface.




Fig. 3: Create a new directory.



Fig. 4: Upload files.

Chapter 9

AmigaOS 4

This page contains all the information you need to get ScummVM up and running on AmigaOS 4.

9.1 What you'll need

- A system running Amiga OS 4

9.2 Installing ScummVM

ScummVM is available for download from the [ScummVM Downloads page](#) or the [OS4 Depot](#).

Download and extract the .lha file.

Run the extracted ScummVM_Install script. This installer guides you through the installation process.

To automatically keep ScummVM up to date through AmiUpdate, run the Autoinstall script.

9.3 Transferring game files

For games on PC or Mac formatted discs, use the original platform to access the data files, and then transfer these to Amiga. Alternatively, if you have external hardware such as a Catweazel floppy disc controller, you might be able to use this to access the files.

ScummVM for Amiga OS has Cloud and LAN functionality, to help manage the transfer of files. See [Connecting a cloud service](#) and [Using the local web server](#).

See [Handling game files](#) for more information about game file requirements.




Fig. 1: The ScummVM installer.

9.4 Controls

Controls can be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common default keyboard shortcuts.

9.5 Paths

9.5.1 Saved games

Games:ScummVM/saves

9.5.2 Configuration file

Games:ScummVM/scummvm.ini

9.6 Settings

For more information about Settings, see the Settings section of the documentation. Only platform-specific differences are listed here.

9.6.1 Audio

The CAMD driver allows the use of MIDI hardware. Select CAMD as the *Preferred device*.

9.7 Known issues

Due to the big-endian nature of Amiga OS, there can sometimes be graphics and sounds issues with games. Check out the Platform Overview [wiki page](#) for a list of compatible engines.

If a game crashes and it's listed as compatible, report it as a *bug*.

Chapter 10

Android

This page contains all the information you need to get ScummVM up and running on an Android device.

10.1 What you'll need

- An Android device running Android 4.1 (Jelly Bean) or newer.

Note: ScummVM has been tested to work up to Android 10. Currently there are some file browsing limitations with Android 11. The ScummVM team are working to resolve these.

10.2 Installing ScummVM

There are two ways to install ScummVM on an Android device; install it from the Google Play Store, or manually download and install the APK package from the ScummVM downloads page.

10.2.1 Installing from the Google Play Store

The latest supported version of ScummVM is on the Google Play Store; search for ScummVM on the Google Play Store and select **Install**.

10.2.2 Manually installing the APK package

On your device, use a web browser app to navigate to the [ScummVM downloads page](#). The recommended download section on the page suggests the correct .apk package, however if it does not, scroll down to select the correct package.

Tip: To find the correct package for your device, find out whether the device has a 32 or 64-bit operating system, and which chipset the device has. Do an internet search using the device model number to find these details.

Click on the correct package to start the download. After it has downloaded, go to the file and tap on it to start the install process. Use either a file manager app, or select the file directly from the web browser downloads. The file manager or the web browser asks for permission to install the package, and after permission is granted, returns to the install.

Note: The downloaded APK package is treated as an app from an unknown source, because it doesn't originate in the Google Play store. To allow unknown apps:

- For Android 7 or lower, go to **Settings > Security > Device Administration**, scroll down to **Device Administration** and enable **Unknown Sources**.
 - For Android 8 or higher, go to **Settings > Apps and Notification** and select **Install Unknown Apps**.
-

10.3 Transferring game files

Transfer all the required game data files to your device, into a folder accessible by the ScummVM app.

ScummVM has built-in Cloud functionality, which lets you connect your Google Drive, OneDrive, Box or Dropbox account. For more information, see the [Connecting a cloud service](#) page. ScummVM also has the ability to run a local web server. For more information, see the [Using the local web server](#) page.

There are a few other options to transfer the game files:

- Copy the files directly onto the microSD card, if the device has one.
- USB transfer from a computer. To complete file transfer by USB cable, tap the **Charging this device via USB notification** when the device is connected. Select **Use USB for** and then **File Transfer**. An Android File Transfer window opens.
- Download games such as freeware games or those from digital distributors directly to your device.

See [Handling game files](#) for more information about game file requirements.

10.4 Controls

10.4.1 Default control mapping

Controls can also be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common keyboard shortcuts.

Touch screen control	Action
One finger tap	Left mouse click
Two finger tap	Right mouse click
One finger touch & hold	Middle mouse click
Long press system Back button	Opens Global Main Menu
Short press system Back button	Skip, or Cancel/Quit in the Launcher
Small keyboard icon (top right)	Opens/closes Virtual keyboard

10.4.2 Touch controls

The touch control scheme can be switched in the global settings. From the Launcher, go to **Options > Control > Touchpad mouse mode**.

- When touchpad mouse mode is off (default), the touch controls are direct. The pointer jumps to where the finger touches the screen.
- When touchpad mouse mode is on, the touch controls are indirect. The finger can be far away from the pointer and still move it, like on a laptop touchpad.
- The pointer speed setting in the [Controls tab](#) affects how far the pointer moves in response to a finger movement.

Two finger tap

To do a two finger tap, hold one finger down and then tap with a second finger.

Immersive Sticky fullscreen mode

ScummVM for Android uses the Immersive Sticky fullscreen mode, which means that the Android system bar is hidden until the user swipes from an edge with a system bar. Swipe from the edge to reveal the system bars. They remain semi-transparent and disappear after a few seconds unless you interact with them. Your swipe also registers in the game, so if you need to swipe from an edge with system bars, your game play is not interrupted.

Virtual keyboard

To open the virtual keyboard, tap on the small keyboard icon at the top right of the screen, or tap on any editable text field. To hide the virtual keyboard, tap the small keyboard icon again, or tap outside the text field.

To display or hide the small keyboard icon, from the Launcher select **Options** and then the **Control** tab. Tick the **Show on-screen control** box to enable the keyboard icon.

10.5 Paths

10.5.1 Saved games

By default, the saved games are saved in the internal app folder. To change the path, go to the [Paths](#) tab in either the global or game-specific settings.

10.5.2 Configuration file

The configuration file is in the internal app folder, and this path cannot be changed.

10.5.3 Accessing the internal app folder

To access the internal app folder, use ScummVM's built-in LAN functionality:

1. From the Launcher, select **Options** and then the **LAN** tab.
2. Select **/root/Path**.
3. Use the file browser to **Go up** to the root of the ScummVM internal app folder.
4. Select the **ScummVM data (int)** shortcut, and tap **Choose**.
5. Run the server to access the `scummvm.ini`` configuration file.

For more information, see the [Using the local web server](#) page.

10.6 Known issues

- On some newer devices, there is an issue if the saved path is outside the app's internal (or external) storage. The ScummVM team is currently working on a fix.
- If ScummVM is uninstalled or downgraded, its internal and external app spaces are fully deleted. If you want to keep saved games use ScummVM's [cloud](#) or LAN functionality to keep those files. Alternatively, change the saved game path to a shared location such as an SD card.

Chapter 11

Atari/FreeMiNT

This page contains all the information you need to get ScummVM up and running on an Atari system.

11.1 What you'll need

- A powerful Atari system or clone; recommended minimum CPU 68060.
- FreeMiNT, TOS or MagiC operating system.

11.2 Installing ScummVM

Binary packages are provided for the m68000 CPU, the m68020 to m68060 range of CPUs, and the Coldfire (FireBee) CPU. All are available for download from the ScummVM [Downloads page](#). To install ScummVM, extract the selected ScummVM archive into a folder on the hard disk.

Run `scummvm.gtp` to start Scummvm. The `scummvm.gtp` command will take *command line options* to set parameters for the ScummVM session.

To run ScummVM from a FreeMiNT Command Line Interface, make the program executable with the following command:

```
chmod +x scummvm.gtp
```

For the best performance, run ScummVM under FreeMiNT, from the command line, and without the AES started.

11.3 Transferring game files

Transfer files to the Atari as you normally would, such as through a network connection or by optical disc.

See *Handling game files* for more information about game file requirements.

11.4 Controls

Controls can be manually configured in the *Keymaps tab*. See the *Keyboard shortcuts* page for common keyboard shortcuts.

11.5 Paths

11.5.1 FreeMiNT

Saved games and the configuration file are found in the user's defined home directory.

11.5.2 MagiC/TOS

Saved games and the configuration file are found in the ScummVM installation directory.

11.6 Settings

For more information, see the Settings section of the documentation. Only platform-specific differences are listed here.

11.6.1 Graphics

For video rendering, define the variable `SDL_VIDEODRIVER=XBIOS` in your environmental variables. Either XBIOS or GEM might be set by default. This is not a ScummVM setting, but rather a system-wide setting.

Tip: XBIOS works better than GEM, because GEM rendering is generally slower.

11.6.2 Audio

Supported audio file formats:

- MP3
- OGG
- FLAC
- Uncompressed audio

11.7 Known issues

- There is no cloud/LAN functionality.
- The Atari built-in MIDI driver (STMIDI) does not work.
- FLAC, OGG and MP3 decoding libraries are extremely CPU intensive and greatly slow down the user experience. ScummVM is best run with uncompressed audio, when available.
- While all supported engines are included in the Atari ScummVM release, not all games will run well due to the lack of resources. For example, the Curse of Monkey Island will run on a CT60-equipped Atari Falcon, but very poorly.

Chapter 12

iOS

This page contains all the information you need to get ScummVM up and running on an iOS device.

12.1 Installing ScummVM

There are two ways to install ScummVM on an iOS device, and the method you use depends on whether or not the device has custom firmware installed.

12.1.1 Devices without custom firmware

To installing ScummVM on an iOS device without custom firmware you need to build the app from the source code, and then install it on your device. While a basic knowledge of the command line would be useful, the following instructions, if followed carefully, can be completed by anyone.

What you'll need

- A Mac computer with Xcode installed. Xcode is a free App, available from the Mac App Store.
- An Apple Developer account. You can sign up for a free account on the [Apple Developer Member Center](#) with your Apple ID.
- The ScummVM [iOS Libraries](#) downloaded, and the zip file extracted.

Note: If you have a free Apple developer account, each build will only be valid for 7 days, which means you will need to repeat these steps and rebuild ScummVM every week.

Step 1: Setting up the Xcode project

The first step is to download the repository containing the code required to build the app. The next steps require use of the command line. Go to **Applications > Utilities > Terminal** and copy and paste the following, then press return. This downloads (clones) the source code into your Home directory, into a folder called scummvm:

```
git clone --depth 1 -b branch-2-2-0 https://github.com/scummvm/scummvm.git
```

Tip: To view the Home directory in the Finder, select **Go > Home** in the menu bar, or press **command+shift+H**.

If you haven't done so before now, open Xcode from the Applications folder, and accept the End User License Agreement. Starting Xcode for the first time also installs the command line tools required.

Create a new directory called build at the same level as the repository you just cloned, using either the Finder, or the command line as follows:

```
mkdir build
```

Copy the contents of the scummvm-ios7-libs-v2 folder you extracted earlier into the build directory, using either the Finder, or the command line as follows:

```
cp -r ~/Downloads/scummvm-ios7-libs-v2/* ~/build/
```

If your downloaded iOS library folder is not in the Downloads folder as it is in the preceding example, change the path to where the folder actually is.

Now let's change the present working directory and then set up the tools required to create the Xcode project:

```
cd scummvm/devtools/create_project/xcode
xcodebuild
```

Step 2: Generating the Xcode project

Change your present working directory to the build directory:

```
cd ~/build
```

It's time to generate the Xcode project. Run the following on the command line:

```
../scummvm/devtools/create_project/xcode/build/Release/create_project ../scummvm --xcode --
↪enable-fluidsynth --disable-nasm --disable-opengl --disable-theora --disable-taskbar --
↪disable-tts --disable-fribidi
```

The resulting directory structure looks like this:

```
Home
|--scummvm
'--build
    |-- include
    |-- lib
    |-- engines
    '-- scummvm.xcodeproj
```

Open the `scummvm.xcodeproj` file from the Finder, or from the command line:

```
open scummvm.xcodeproj
```

Step 3: Building the ScummVM app

When Xcode is open, connect a device to install ScummVM onto. At the top of the window, select **ScummVM-iOS** and then select the device you just connected. You will need to “Trust” the device for it to show up on the list of connected devices.

The last step before building ScummVM is to change the bundle identifier and manage signing. Click on the **scummvm** project in the left pane, and then click on **ScummVM - iOS** under **TARGETS**. On the menu bar above, click on **General**. Under **Identity** there is a field labeled **Bundle Identifier**. Enter a unique identifier in reverse-DNS format. This can be as simple as `com.yournamehere`.

Next to **General**, click on **Signing & Capabilities**. Under **Signing**, tick the **Automatically manage signing** box, and select your developer account from the **Team** dropdown menu.

If you have not added your developer account to Xcode, do this now. Click **Add an Account** in the dropdown menu.

In the upper left-hand corner, press the play button to build ScummVM. When the build is finished, it launches on your connected device.

If ScummVM does not launch and you get an error message advising that the app failed to launch due to an invalid code signature, inadequate entitlements or because its profile has not been explicitly trusted by the user, you need to trust the apps that you have built. On your iOS device, go to **Settings > General > Device Management > Developer App > Trust “Apple Development:yourAppleIDhere” > Trust**.

12.1.2 Devices with custom firmware

What you'll need

- An iOS device with custom firmware installed (jailbroken). How to jailbreak a device is outside the scope of this documentation.
- A file manager app such as Filza installed on the device.

Downloading and installing ScummVM

Go to the [ScummVM downloads page](#) and download the recommended .deb or .ipa package. When the device asks how to open the file, choose Filza.

Ensure the package is saved somewhere in the /var/mobile/ directory. It defaults to /var/mobile/Documents/, which is fine. Tap on the file and then tap **Install** in the upper right corner to install ScummVM.

Restart your device for the install to complete.

12.2 Transferring game files

There are multiple ways to transfer game files to your iOS device.

ScummVM has built-in cloud functionality, which lets you connect your Google Drive, OneDrive, Box or Dropbox account. For more information, see the [Connecting a cloud service](#) page. ScummVM also has the ability to run a local web server. For more information, see the [Using the local web server](#) page.

Note: ScummVM's cloud functionality does not currently support iCloud, however you can upload game folders to your iCloud and then use the Files app on your iOS device to copy these folders into the local ScummVM folder.

Another way to transfer files (for macOS Catalina and newer) to your device is by using the Finder while your device is connected to your Mac. In the Finder app on your Mac, navigate to **Locations** in the left pane, and click on the connected device. Click on **Files**, then drag the folder containing the game files into the **ScummVM** folder. For older versions of macOS, and for Windows users, file transfer can be done in iTunes.

See [Handling game files](#) for more information about game file requirements.

12.3 Controls

Game Controller Mapping	
Touch screen control	Action
One finger tap	Left mouse click
<i>Two finger tap</i>	Right mouse click
<i>Two finger double tap</i>	ESC
Two finger swipe (bottom to top)	Toggles <i>Click and drag mode</i>
Two finger swipe (left to right)	Toggles between touch direct mode and touchpad mode.
Two finger swipe (top to bottom)	Global Main Menu
Three finger swipe	Arrow keys
Pinch gesture	Enables/disables keyboard
Keyboard spacebar	Pause

12.3.1 Touch controls

The touch control scheme can be switched in the global settings. From the Launcher, go to **Options > Control > Touchpad mouse mode**.

- When touchpad mouse mode is off, the touch controls are direct. The pointer jumps to where the finger touches the screen.
- When touchpad mouse mode is on, the touch controls are indirect. The finger can be far away from the pointer and still move it, like on a laptop touchpad.
- The pointer speed setting in the *Controls tab* affects how far the pointer moves in response to a finger movement.

Two finger tap

For a two finger tap, hold one finger down and then tap with a second finger.

Two finger double tap

For a two finger double tap, hold one finger down and then double tap with a second finger.

Click and drag mode

Simulates a left mouse click when you touch the screen. The mouse pointer drags to wherever you slide your finger, and releases where you lift your finger.

If you press down a second finger in this mode, it releases the simulated left mouse button, and presses down the simulated right mouse button. The right mouse button is released when you lift your finger again.

Keyboard

If no external keyboard is connected, the pinch gesture shows and hides the onscreen keyboard. When an external keyboard is connected, the pinch gesture enables/disables inputs from the external keyboard.

12.4 Paths

12.4.1 Saved games

`/var/mobile/Library/ScummVM/Savegames/` if the device is jailbroken, or `Savegames/` in the ScummVM folder for a non-jailbroken device. Access this folder through the Finder or iTunes.

12.4.2 Configuration file

`/var/mobile/Library/ScummVM/Preferences` if the device is jailbroken, or `Preferences` in the ScummVM folder for a non-jailbroken device. Access this folder through the Finder or iTunes.

Chapter 13

Nintendo 3DS

This page contains all the information you need to get ScummVM up and running on a Nintendo 3DS.

13.1 What you'll need

- A Nintendo 3DS with a Homebrew Launcher or custom firmware. How to enable homebrew is outside the scope of this documentation.

13.2 Installing ScummVM

Download the Nintendo 3DS package from the [ScummVM Downloads page](#). Extract the archive.

There are two ways to install ScummVM: using the 3DSX format, or the CIA format.

13.2.1 Using the 3DSX format

Copy the extracted files to your SD card into the `/3ds/scummvm` directory.

Launch ScummVM using the Homebrew Launcher.

13.2.2 Using the CIA format

Use any CIA installation software to install the `scummvm.cia` file.

The CIA format requires a DSP binary dump saved on your SD card as `/3ds/dspfirm.cdc`. This is not an optional step, because without this you will not have proper audio support. Documenting this process is outside the scope of this documentation.

13.3 Transferring game files

Transfer game folders onto the SD card. The exact location is not important.

ScummVM for the Nintendo 3DS also has cloud functionality. See [Connecting a cloud service](#).

See [Handling game files](#) for more information about game file requirements.

13.4 Controls

13.4.1 Default control mapping

Controls can also be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common keyboard shortcuts.

Game Controller Mapping:	
Button	Action
Circle Pad	Moves the cursor
R + Circle Pad	Slow Mouse
	Left mouse button
	Right mouse button
	Opens the virtual keyboard
	ESC
Control Pad	Keypad cursor keys
L Button	Toggles magnify mode on/off
R Button	Toggles between hover/drag modes
START	Opens global main menu
SELECT	Opens 3DS config menu

13.4.2 Hover mode

When using the touchscreen, hover mode simulates the movement of the mouse. You can click with taps, however you can't drag or hold down a mouse button unless you use the buttons mapped to the right/left mouse buttons.

13.4.3 Drag mode

Simulates the click and release of the mouse buttons every time you touch and release the touchscreen. At the moment, this is only a left mouse button click.

13.4.4 Magnify mode

Due to the low resolutions of the 3DS screens (400x240 for the top, and 320x240 for the bottom), games that run at a higher resolution will inevitably lose some visual detail from being scaled down. This can result in situations where essential information, such as text, is indiscernable.

Magnify mode increases the scale factor of the top screen back to 1, but the bottom screen remains unchanged. The touchscreen can then be used to change which part of the game display is being magnified. This can be done even in situations where the cursor is disabled, such as during full-motion video segments.

When activating magnify mode, touchscreen controls are automatically switched to *Hover mode* to reduce the risk of the user accidentally inputting a click when changing the magnified area with the stylus. Clicking can still be done as in normal hover mode. Turning off magnify mode will revert controls back to what was used previously. It will also restore the top screen's previous scale factor.

Magnify mode can only be used when the following conditions are met:

- In the 3DS config menu, the **Use Screen** option is set to **Both**.
- The horizontal and/or vertical in-game resolution is greater than that of the top screen.
- You're playing a game.

Magnify mode cannot be used in the Launcher menu.

13.5 Paths

13.5.1 Saved games

`sdmc:/3ds/scummvm/saves/`

13.5.2 Configuration file

`sdmc:/3ds/scummvm/scummvm.ini`

13.6 Settings

For more information about Settings, see the Settings section of the documentation. Only platform-specific differences are listed here.

13.6.1 The 3DS config menu




Fig. 1: The 3DS config menu.

Show mouse cursor Toggles a visible mouse cursor on/off.

Stretch to fit Stretches the image to fit the screen

Snap to edges The 3DS touch screen has difficulty reaching the very end of the screen. With this option enabled, if you're within a few pixels of the edge the cursor snaps to the edge.

Use Screen: Sets whether ScummVM uses the **Top**, **Bottom** or **Both** screens.

C-Pad Sensitivity Sets the sensitivity of the Circle Pad.

13.6.2 Audio

Supported audio file formats:

- MP3
- OGG
- OGG
- Uncompressed audio

13.7 Known issues

Some games are not playable due to the slow CPU speed on the 3DS. If there are any games that run really slowly, this is considered a hardware limitation, not a bug.

Chapter 14

Nintendo Switch

This page contains all the information you need to get ScummVM up and running on a Nintendo Switch.

14.1 What you'll need

- A homebrew-enabled Nintendo Switch console. How to enable homebrew is outside the scope of this documentation.

14.2 Installing ScummVM

The Nintendo Switch package is available for download on the ScummVM [Downloads page](#).

Download the zip file to a computer, and extract the files.

Copy the extracted scummvm folder to your Nintendo Switch microSD card, into the /switch/ folder.

14.3 Transferring game files

Copy the folders containing game files into the /switch/scummvm/ folder on the microSD card.

ScummVM on the Nintendo switch supports *cloud functionality*.

See *Handling game files* for more information about game file requirements.

14.4 Controls

14.4.1 Default control map

These controls can also be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common keyboard shortcuts.

Button	Action
Left stick	Mouse
Left stick + R button	Slow Mouse
	Left mouse button
	Right mouse button
Directional buttons	Keypad 'Cursor' Keys
Directional buttons + R button	Diagonal Keypad 'Cursor' Keys
L button	Game menu (F5)
R button	Shift
	Period
+ R button	Space
	Escape
+ R button	Return
	Global main menu (GMM)
	Toggle virtual keyboard
+ R button	AGI predictive input dialog

Touch Controls (Touchpad Mouse Mode Off, Default)	
Touch	Action
Short single finger tap	Move pointer to finger position and left mouse button click
Short second finger tap while holding one finger	Move pointer to first finger position and right mouse button click
Single finger drag	Move pointer directly with finger
<i>Two finger drag</i>	Move pointer while left mouse button is held down (drag and drop). The pointer directly follows the first finger. The drag is ended when the last finger is removed.
<i>Three finger drag</i>	Move pointer while right mouse button is held down (drag and drop). The pointer directly follows the first finger. The drag is ended when the last finger is removed.

Touch Controls (Touchpad Mouse Mode On)	
Touch	Action
Short single finger tap	Left mouse button click
Short second finger tap while holding one finger	Right mouse button click
Single finger drag	Move pointer indirectly with finger, pointer speed can be adjusted in control settings
<i>Two finger drag</i>	Move pointer while left mouse button is held down (drag-and-drop). The pointer motion is affected by the first finger. The drag is ended when the last finger is removed.
<i>Three finger drag</i>	Move pointer while right mouse button is held down (drag-and-drop). The pointer motion is affected by the first finger. The drag is ended when the last finger is removed.

14.4.2 Keyboard and mouse support

Physical USB mice and keyboards work on the Switch and are supported by ScummVM. All keyboards work but not all mice work. A mouse compatibility list is available on this [Google Sheet](#).

14.4.3 Touch support

For multi-touch gestures, the fingers have to be far enough apart from each other that the Switch does not recognize them as a single finger, otherwise the pointer jumps around.

The touch control scheme can be switched in the global settings. From the Launcher, go to **Options > Control > Touchpad mouse mode**.

- When touchpad mouse mode is off (default), the touch controls are direct. The pointer always jumps to where the finger touches the screen.
- When touchpad mouse mode is on, the touch controls are indirect. The finger can be far away from the pointer and still move it, like on a laptop touchpad.
- The pointer speed setting in the [Controls tab](#) affects how far the pointer moves in response to a finger movement.

Two finger drag

Hold down two fingers to initiate a drag-and-drop feature. The two finger drag simulates the left mouse button being held down.

- The first finger affects mouse motion during the drag, the second finger can be removed without affecting the drag.
- When the last finger is removed, the left mouse button is released and the drag is over.
- The second finger can be anywhere, it doesn't have to be close to the first finger, and it doesn't have to be put down simultaneously with the first finger.

Three finger drag

Hold down the three fingers to initiate a drag-and-drop feature. The three finger drag simulates the right mouse button being held down.

14.5 Paths

14.5.1 Saved games

`/switch/scummvm/saves`

14.5.2 Configuration file

`/switch/scummvm/scummvm.ini`

14.6 Settings

For more information, see the Settings section of the documentation. Only platform-specific differences are listed here.

14.6.1 Audio

Supported devices:

- MT-32 emulator
- FluidSynth (General MIDI emulator)
- AdLib emulator

Supported audio file formats:

- MP3

- OGG
- FLAC
- Uncompressed audio

14.6.2 Controls

See the *Touch support* section.

Chapter 15

PlayStation 3

This page contains all the information you need to get ScummVM up and running on a PlayStation 3.

15.1 What you'll need

- A Homebrew enabled Playstation 3 console. How to enable homebrew is outside the scope of this documentation.
- A USB drive
- A computer

15.2 Installing ScummVM

Download the Playstation 3 package from the [ScummVM Downloads page](#). Copy the .pkg file to a USB drive.

Plug the USB drive into the PS3. Go to the XMB, then go to **Games > Install Package** to install the ScummVM package.

To launch ScummVM, go to the XMB, then go to **Games > PlayStation 3 > ScummVM**.

15.3 Transferring game files

Games can be launched from either a USB drive, or from the internal hard drive. The hard drive has better performance.

To copy game files to the hard drive, use the USB drive, or use ScummVM's [cloud functionality](#).

See [Handling game files](#) for more information about game file requirements.

15.4 Controls

Controls can also be manually configured in the *Keymaps tab*. See the *Keyboard shortcuts* page for common keyboard shortcuts.

15.4.1 Default control map

Touchscreen:	
Buttons/Control	Action
Left stick	Moves pointer
	Left mouse button
	Right mouse button
	Game menu
	Esc
START	Global Main Menu
SELECT	Toggle virtual keyboard
L1 button	AGI predictive input dialog

15.5 Paths

15.5.1 Saved games

``/hdd0/game/SCUM12000/USRDIR/saves/`

15.5.2 Configuration file

`/hdd0/game/SCUM12000/USRDIR/scummvm.ini`

15.6 Settings

For more information, see the Settings section of the documentation. Only platform-specific differences are listed here.

15.6.1 Audio

Supported audio file formats:

- MP3
- OGG
- FLAC
- Uncompressed audio

Chapter 16

PlayStation Portable

This page contains all the information you need to get ScummVM up and running on a PSP.

16.1 What you'll need

- A homebrew-enabled PSP. How to enable homebrew is outside the scope of this documentation.
- A computer to download and extract the install files.

16.2 Installing ScummVM

The PSP package is available for download ScummVM's [Downloads page](#).

Download the zip file to a computer, and extract the files.

Connect the PSP to the computer by USB cable. Go to **Settings > USB Connection** on the PSP. Ensure the **USB Device** option is set to **Memory Stick**. The computer automatically opens the root folder of the PSP. Alternatively, if you have a Memory Stick adapter, copy the files directly to the Memory Stick.

Copy the extracted `scummvm` folder to your PSP, into the `/PSP/GAME/` folder.

Go to **Game > Memory Stick** and choose **ScummVM** to launch ScummVM!

16.3 Transferring game files

Transfer game files onto the PSP as described in the installation section above. They can be copied to any folder; location doesn't matter.

See [Handling game files](#) for more information about game file requirements.

16.4 Controls

16.4.1 Default control map

These controls can also be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common keyboard shortcuts.

Game Controller Mapping	Action
Button	Modifier key
R button	ESC
L button	Mouse movement
Analog stick	Fine mouse movement
Analog stick + R button	Arrow keys
Directional buttons	Diagonal arrow keys
Directional buttons + R button	Enter
	Left Mouse Button
	Right Mouse Button
	Period
+ R button	Spacebar
SELECT	Shows/Hides the virtual Keyboard. Hold down with Directional buttons to move the keyboard.
SELECT + R button	Shows Image Viewer
START	Global Main Menu
START + R button	F5

Virtual Keyboard Mode	
START	Enter. Also exits virtual keyboard mode
SELECT	Exits the virtual keyboard mode
R button	Input: lowercase/uppercase letters (press to toggle)
L button	Input: numbers/symbols (press to toggle)
Directional buttons	Selects square of characters (up, down, left or right)
and L/R buttons	Chooses a specific character in the square. The four center characters are chosen by the button in the corresponding position. The 2 top characters are chosen by the L/R buttons.
Analog stick	Moves in a direction (left/right/up/down)

Image Viewer	
Left/right directional buttons	Previous/next image
Up/down directional buttons	Zooms in/out
Analog stick	Moves around the image
L/R buttons + START	Exits image viewer

1st Person Game Mode	
+ R button + L button	Enables 1st Person Mode
	Modifier key (instead of R button)
L/R button	Strafes left/right
Directional buttons left/right	Turns left/right
+ Directional buttons	F1/F2/F3/F4
+ SELECT	Image Viewer
+ START	Esc

16.5 Settings

For more information, see the Settings section of the documentation. Only platform-specific differences are listed here.

16.5.1 Audio

Supported audio file formats:

- MP3
- OGG
- Uncompressed audio

Tip: Games run faster if audio files are in the .mp3 file format.

16.6 Paths

16.6.1 Saved games

ms0:/scummvm_savegames/

16.6.2 Configuration file

ms0:/scummvm.ini

16.7 Known issues

- Plugin files are not interchangeable between ScummVM versions. You must copy all the plugin files found in the /PSP/GAME/scummvm/plugin/ folder for every new version you install. If ScummVM crashes on startup, delete the existing plugin files in the plugin directory and copy the new ones again.
- If the virtual keyboard does not show up on the screen, ensure the kbd.zip file is in the scummvm folder.

Chapter 17

PlayStation Vita

This page contains all the information you need to get ScummVM up and running on a PS Vita.

17.1 What you'll need

- A homebrew-enabled PS Vita console with [Vitashell](#) installed. How to enable homebrew is outside the scope of this documentation.

17.2 Installing ScummVM

The PS Vita package is available for download on the ScummVM [Downloads](#) page.

Copy the .vpk to the PS Vita and install it using VitaShell.

17.3 Transferring game files

There are a few ways to transfer game files to the PS Vita.

Use VitaShell to transfer the files by USB or FTP, or use SD2Vita to transfer the files directly to the microSD card.

Folders containing game files can be copied anywhere on the SD card.

ScummVM on the PS Vita supports [cloud functionality](#).

See [Handling game files](#) for more information about game file requirements.

17.4 Controls

17.4.1 Default control map

These controls can also be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common keyboard shortcuts.

Game Controller Mapping	
Button	Action
Left stick	Mouse
Left stick + R button	Slow Mouse
	Left mouse click
	Right mouse click
Directional buttons	Keypad 'Cursor' Keys
Directional buttons + R button	Diagonal Keypad 'Cursor' Keys
L button	Game menu (F5)
R button	Shift
	Period (.)
R button +	Spacebar
	Escape
R button +	Return
START	Global main menu (GMM)
SELECT	Toggle virtual keyboard
SELECT + R button	AGI predictive input dialog

Front Touchscreen Controls, always enabled	
Touch	Action
One finger tap	Moves pointer to finger position and left mouse click
Two finger tap	Moves pointer to first finger position and right mouse click
Single finger drag	Moves pointer directly with finger
<i>Two finger drag</i>	Moves pointer while left mouse button is held down (drag-and-drop).
<i>Three finger drag</i>	Moves pointer while right mouse button is held down (drag-and-drop).

Back Touchpad Controls, enabled through settings	
Touch	Action
One finger tap	Left mouse button click
Two finger tap	Right mouse button click
Single finger drag	Moves pointer indirectly with finger, pointer speed can be adjusted in control settings
<i>Two finger drag</i>	Moves pointer while left mouse button is held down (drag-and-drop).
<i>Three finger drag</i>	Moves pointer while right mouse button is held down (drag-and-drop).

17.4.2 Keyboard and mouse support

Real bluetooth mice and keyboards work on the Vita and are supported by ScummVM. Go to **Settings > Devices** on the Vita home screen to pair your devices.

Note: Not all bluetooth keyboards or mice pair successfully with the Vita. The ScummVM team tested the Jelly Bean BT keyboard and mouse combo (ASIN:B06Y56BBYP) and with the standalone Jelly Comb Bluetooth Wireless Mouse (ASIN:B075HBDWCF).

17.4.3 Touch support

For multi-touch gestures, the fingers have to be far enough apart from each other that the Vita will not recognize them as a single finger, otherwise the pointer will jump around.

Touchpad mouse mode

The touch control scheme can be switched in the global settings. Go to **Options > Control:**

- When **Touchpad mouse mode** is off:
 - The touch controls are direct, which means the pointer always jumps to the finger position.
 - The rear touch pad is disabled.
- When **Touchpad mouse mode** is on:
 - The touch controls are indirect. The finger can be far away from the pointer and still move it, like on a laptop touchpad.
 - The pointer speed setting in the *Control tab* affects how far the pointer moves in response to a finger movement.
 - The rear touch pad is enabled.

The front touchscreen uses the direct mode by default, but this can be changed by editing the *configuration file* with the following keyword:

frontpanel_touchpad_mode

When set to true, the touch controls on the front touchscreen are indirect.

Two finger tap

For a two finger tap, hold one finger down and then tap with a second finger.

Two finger drag

Hold down two fingers to initiate a drag-and-drop feature. The two finger drag simulates the left mouse button being held down.

- The first finger affects mouse motion during the drag, the second finger can be removed without affecting the drag.
- When the last finger is removed, the left mouse button is released and the drag is over.
- The second finger can be anywhere, it doesn't have to be close to the first finger, and it doesn't have to be put down simultaneously with the first finger.

Three finger drag

Hold down the three fingers to initiate a drag-and-drop feature. The three finger drag simulates the right mouse button being held down.

17.5 Paths

17.5.1 Saved games

ux0:/data/scummvm/saves

17.5.2 Configuration file

ux0:/data/scummvm/scummvm.ini

17.6 Settings

For more information, see the Settings section of the documentation. Only platform-specific differences are listed here.

17.6.1 Audio

Supported audio file formats:

- MP3
- OGG
- FLAC
- Uncompressed audio

17.6.2 Controls

See the *Touch support* section.

17.7 Known Issues

- MT-32 emulation is not available on the PS Vita.

Chapter 18

RISC OS

This page contains all the information you need to get ScummVM up and running on the RISC operating system.

18.1 What you'll need

- A system running RISC OS 5
- The [SharedUnixLibrary](#), [DRenderer](#) and [Iconv](#) modules installed. [SharedUnixLibrary](#) and [DRenderer](#) can be installed using [Packman](#).

18.2 Installing ScummVM

Download the RISC OS package from the [ScummVM Downloads page](#).

Use a tool such as SparkFS to extract the archive. It is important that the archive is not extracted on any other system, because this results in a loss of file type information. ScummVM requires the file type information to run properly.

18.3 Transferring game files

Copy data files directly from the original discs on machines that have CD and/or floppy drives, or use a USB drive to transfer the files from another system.

See [Handling game files](#) for more information about game file requirements.

18.4 Controls

Controls can be manually configured in the [Keymaps tab](#). See the [Keyboard shortcuts](#) page for common default keyboard shortcuts.

18.5 Paths

18.5.1 Saved games

`<Choices$Write>.ScummVM.Saves`

18.5.2 Configuration file

`<Choices$Write>.ScummVM.scummvmrc`

The `<Choices$Write>` environment variable is usually `$.!Boot.Choices`.

18.6 Settings

For more information about settings, see the Settings section of the documentation. Only platform-specific differences are listed here.

There is one additional configuration option, *enable_reporter*. When set to true in [Configuration file](#), log messages are sent to the [!Reporter](#) application. This is useful mostly for developers.

18.7 Known issues

- ScummVM for RISC OS does not have cloud or LAN functionality.
- FluidSynth is not supported.
- ScummVM is not compatible with RISC OS 3, 4 or 6.

Chapter 19

Sega Dreamcast

This page contains all the information you need to get ScummVM up and running on a Sega Dreamcast.

19.1 What you'll need

- A CD-R disc (80min/700mb).
- A CD-RW drive.
- A computer running Windows.
- Software to create a bootable disc image, such as [BootDreams](#)
- CD burning software such as Nero Burning ROM, ImgBurn or Alcohol120%.

19.2 Running ScummVM

There are two ways to get ScummVM running on the Dreamcast:

1. Download the ready-to-go Nero Image and Demos package and burn the extracted .nrg image to a CD-R using Nero Burning ROM.
2. Download the Dreamcast plain files package and use the extracted files to create a custom disc image to burn to a CD-R.

Both packages are available from the ScummVM [Downloads page](#)

19.2.1 Creating a disc from the Dreamcast Nero Image and Demos package

Use Nero Burning ROM to burn the .nrg file contained in the package to a CD-R disc.

19.2.2 Creating a disc from the Dreamcast plain files package

Create a directory on your computer. In this example, the directory is called ScummVMDC.

Copy the downloaded SCUMMVM.BIN and IP.BIN files into the ScummVMDC directory. These are the main boot and engine files required for ScummVM to run.

The .PLG files in the plain files package are the plugins that are required to run the games. For the best performance, only include the plugins for games you want to play. For example, if you want to play LucasArts games, include SCUMM.PLG.

In the plain files package there are also .DAT files. These files might be listed as required Datafiles on the [Datafiles wiki page](#).

Copy the required .PLG and .DAT files into the root of the ScummVMDC directory.

Next, make a new directory for each game. In this example, all the required Day of the Tentacle data files have been copied into a subdirectory named DOTT.

Our file structure now looks like this:

```
ScummVMDC
|--DOTT
|   |-- MONSTER.SOU
|   |-- TENTACLE.000
|   `-- TENTACLE.001
|--IP.BIN
|-- SCUMM.PLG
`-- SCUMMVM.BIN
```

The next step is to create a bootable disc image from the ScummVMDC folder.

Use Bootdreams to create either a Discjuggler, Nero or Alcohol120% disc image.

1. Choose the preferred disc image type by clicking on the corresponding icon at the top of the window.
2. Choose the ScummVMDC folder as the **Selfboot folder**
3. Enter a title for the disc image in the **CD label** field.
4. Leave the **Disc format** as **Audio/Data**
5. Click **Process** to create the disc image.

To burn the resulting image to disc, use any software capable of using those image formats, such as Nero Burning ROM for NRG, Alcohol120% for MDS, and Padus DiscJuggler or ImgBurn for CDI disc images.



Tip: The image created from the plain files package can also be used with Optical Disc Emulators and similar external hardware.

Caution: Use the lowest possible burning speed for best results; the Dreamcast is an older system and as such can have problems reading discs burned at high speeds. If available, the 4x speed is ideal. Ensure that you use good quality discs from a reputable manufacturer. If possible, use archival grade discs.

19.3 Transferring game files

Game files can be included on the same CD as the ScummVM binary file, or on a separate disc.

The Dreamcast port does not use the normal ScummVM Launcher. It uses its own custom graphical user interface, which automatically scans the disc for games, and adds the games to a games list through ScummVM's built-in autodetection.

ScummVM for the Dreamcast supports disc swapping from the GUI. It rescans after a new disc is inserted and repopulates the games list.

See [Handling game files](#) for more information about game file requirements.

19.4 Controls

19.4.1 Default control map

Game Mapping:	Controller		
Button		Action	Notes
Joystick		Moves pointer	
Directional pad		Moves pointer slowly	Also controls the on-screen keyboard
		Left Click	
		Right Click	
		Spacebar	Pause
Start		F5	Load and save
Trigger L		Toggles the virtual keyboard on/off	
		5	For boxing in Indiana Jones and the Last Crusade
+ Directional pad		1, 2, 3, 4, 6, 7, 8, 9	For boxing in Indiana Jones and the Last Crusade

The mouse cursor is controlled with the standard Dreamcast controller. The Dreamcast mouse and keyboard peripherals are also supported.

19.5 Paths

19.5.1 Saved games

The Visual Memory Unit (VMU) is used to save and load games.

Autosave is enabled on the Dreamcast, so each game will use some memory blocks (between 2 and 13) for the autosave in save slot 0.

When a game is saved, the VMU beeps, and a prompt is displayed on the screen to let you know that the game has been saved.

Games are saved and loaded through the built-in game menus.

19.5.2 Configuration file

ScummVM for the Dreamcast does not use a configuration file.

19.6 Settings

There is no way to change ScummVM settings on the Dreamcast.

19.7 Known issues

- The Dreamcast has no external storage medium, and only has 16MB of RAM. As such, the Dreamcast port of ScummVM does not support The Curse of Monkey Island or the Dig. The resources required for these games are too great for the Dreamcast to handle. Full Throttle is not completable.
- There is currently no way to manually add games to the games list. The autodetect feature usually works well, but sometimes games will show up on the list twice, incorrect games will show up with the correct game, and, quite rarely, the game will not show up on the list at all.
- Some games, for example SPY Fox 1: Dry Cereal, use filenames which are incompatible with the ISO 9660 filesystem standard. The Dreamcast port does not support filename extensions like RockRidge or Joliet, so the CD mastering software needs to be instructed not to change the filenames to comply to ISO 9660, or the engine will not be able to open the files.

Chapter 20

Game

Use the Game tab to display and change information about how the game is identified by ScummVM.

From the Launcher, highlight a game on the games list, then select **Edit Game**. The **Game** tab is the first tab shown.

All settings can also be changed in the *Configuration file*. The configuration key is listed in italics after each setting description.

ID Shows the short name of the game. This ID can be used for launching the game from the command line.

gameid

Name Shows the full title of the game, as well as some basic information such as original platform and language.

description

Language For games that were released with support for multiple languages, this options changes the language of the game. For games that have a single language hardcoded, this option does not change the language of the game, it only affects the subtitles. Select the correct language to ensure that subtitles display correctly, especially for non-English games.

language

Platform Specifies the original platform of the game.

platform




Fig. 1: The Game tab in the game-specific settings

Chapter 21

Engine

Use the Engine tab to change settings that are unique to the game being played.

From the Launcher, highlight a game on the games list, select **Edit Game**, and then select the **Engine** tab. This tab is not available for all games.

To find out which engine powers your game, have a look at the ScummVM Supported Games [wiki page](#).

Engines: *ADL* | *AGI* | *BLADERUNNER* | *CGE* | *CINE* | *DRASCULA* | *DREAMWEB* | *HDB* | *HOPKINS* | *KYRA* | *LURE* | *MADS* | *NEVERHOOD* | *SCI* | *SCUMM* | *SHERLOCK* | *SKY* | *SUPERNOVA* | *TOLTECS* | *WINTERMUTE* | *XEEN* |

All settings can also be changed in the *Configuration file*. The configuration key is listed in italics after each setting description.

21.1 ADL

TV emulation Emulates the composite output to an NTSC TV.

ntsc

Color Graphics Uses color graphics instead of monochrome graphics.

color

Show scanlines Darkens every other scanline to mimic the look of a CRT display.

scanlines

Always use sharp monochrome text Does not emulate NTSC artifacts for text.

monotext



Fig. 1: The Engine tab in the game-specific settings

21.2 AGI

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Use an alternative palette Uses an alternative palette, common to all Amiga games.

altamigapalette

Mouse support Enables mouse support for movement and in game menus.

mousesupport

Use Hercules hires font Uses the Hercules hi-resolution font, when the font file is available.

herculesfont

Pause when entering commands Shows a command prompt window and pauses the game, instead of a real-time prompt.

commandpromptwindow

Add speed menu Adds a game speed menu, similar to the PC version.

apple2gs_speedmenu

21.3 BLADERUNNER

Sitcom mode Adds laughter after the actor's line or narration.

sitcom

Shorty mode Shrinks the actors and makes their voices high pitched.

shorty

Frame limiter high performance mode Avoids use of `delayMillis()` function. This mode might result in high CPU usage.

nodelaymillisfl

Max frames per second limit Targets a maximum of 120 frames per second (fps). When disabled, the game targets 60 fps.

frames_per_secondfl

Disable McCoy's quick stamina drain When running, McCoy won't start slowing down as soon as the player stops clicking the mouse.

disable_stamina_drain

21.4 CGE

Color Blind Mode Enables Color Blind Mode by default.

enable_color_blind

21.5 CINE

Use original save/load screen Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Use transparent dialog boxes in 16 color scenes Uses transparent dialog boxes in 16 color scenes even if the original game version did not support them.

transparentdialogboxes

21.6 DRASCULA

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

21.7 DREAMWEB

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Use bright palette mode Displays graphics using the game's bright palette.

bright_palette

21.8 HDB

Enable cheat mode Enables debug info and level selection.

hypercheat

21.9 HOPKINS

Gore Mode Enables Gore Mode when available.

enable_gore

21.10 KYRA

Enable studio audience Studio audience adds an applause and cheering sounds whenever Malcolm makes a joke.

studio_audience

Skip support Lets the user skip text and cutscenes.

skip_support

Enable helium mode Makes characters sound like they inhaled Helium.

helium_mode

Enable smooth scrolling when walking Makes scrolling smoother when changing from one screen to another.

smooth_scrolling

Enable floating cursors Changes the cursor when it floats to the edge of the screen to a directional arrow. Click to walk in that direction.

floating_cursors

Suggest save names Fills in an autogenerated save game description into the input prompt.

auto_savenames

HP bar graphs Enables hit point bar graphs.

hpbargraphs

Fight Button L/R Swap Swaps the buttons so that the left button attacks, and the right button picks up items.

mousebtswap

21.11 LURE

TTS Narrator Uses text-to-speech to read the descriptions, if text-to-speech is available.

tts_narrator

21.12 MADS

Easy mouse interface Shows object names when the mouse pointer is held over the object.

EasyMouse

Animated inventory items Animates the inventory items.

InvObjectsAnimated

Animated game interface Animates the game interface.

TextWindowAnimated

Naughty game mode Enables naughty game mode.

NaughtyMode

Graphics dithering Enables graphics dithering.

GraphicsDithering

21.13 NEVERHOOD

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Skip the Hall of Records storyboard scenes Lets the player skip past the Hall of Records storyboard scenes.

skiphallofrecordsscenes

Scale the making of videos to full screen Scales the making-of videos, so that they use the whole screen.

scalemakingofvideos

21.14 QUEEN

Alternate intro Plays the alternate intro for Flight of the Amazon Queen.

alt_intro

21.15 SCI

Skip EGA dithering pass (full color backgrounds) Skips dithering pass in EGA games. Graphics are shown with full colors.

disable_dithering

Enable high resolution graphics Enables high resolution graphics and content.

enable_high_resolution_graphics

Enable black-lined video Draws black lines over videos to increase their apparent sharpness.

enable_black_lined_video

Use high-quality video scaling Uses linear interpolation when upscaling videos, where possible.

enable_hq_video

Use high-quality “LarryScale” cel scaling Uses special cartoon scaler for drawing character sprites.

enable_larryscale

Prefer digital sound effects Prefers digital (sampled) sound effects instead of synthesized ones.

prefer_digitalsfx

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Use IMF/Yamaha FB-01 for MIDI output Uses an IBM Music Feature card or a Yamaha FB-01 FM synth module for MIDI output.

native_fb01

Use CD audio Uses CD audio instead of in-game audio, if available.

use_cdaudio

Use Windows cursors Uses the Windows cursor (smaller and monochrome) instead of the DOS cursor.

windows_cursors

Use silver cursors Uses the alternate set of silver cursors instead of the normal golden cursors.

silver_cursors

Upscale videos Upscales videos to double their size

enable_video_upscale

Enable content censoring Enables the game's built-in optional content censoring.

enable_censoring

21.16 SCUMM

Show Object Line Show the names of objects at the bottom of the screen.

object_labels

Use NES Classic Palette Uses a more neutral color palette that closely emulates the NES Classic.

mm_nes_classic_palette

21.17 SHERLOCK

Use original load/save screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

Pixellated scene transitions Enables randomized pixel transitions between scenes.

fade_style

Don't show hotspots when moving mouse Only shows hotspot names after you click on a hotspot or action button.

help_style

Show character portraits Shows portraits of the characters when the characters converse.

portraits_on

Slide dialogs into view Slides UI dialogs into view.

window_style

Transparent windows Shows windows with a partially transparent background.

transparent_windows

TTS Narrator Uses text-to-speech to read the descriptions, if text-to-speech is available.

tts_narrator

21.18 SKY

Floppy intro Uses the floppy version's intro (CD version only)

alt_intro

21.19 SUPERNOVA

Improved mode Removes some repetitive actions, and adds the possibility to change verbs by keyboard.

improved

21.20 TOLTECS

Use original save/load screens Uses the original save/load screens instead of the ScummVM screens.

originalsaveload

21.21 WINTERMUTE

Show FPS-counter Shows the current number of frames per second in the upper left corner.

show_fps

Sprite bilinear filtering (SLOW) Applies bilinear filtering to individual sprites.

bilinear_filtering

21.22 XEEN

Show item costs in standard inventory mode Shows item costs in standard inventory mode, which lets the value of items be compared.

ShowItemCosts

More durable armor Armor won't break until character is at -80HP, instead of the default -10HP.

DurableArmor

Chapter 22

Graphics

Use the Graphics tab to change how games look when they are played.

To change settings globally:

From the Launcher, select **Options**. The **Graphics** tab is the first tab shown.

To change settings for a specific game:

Highlight the game in the games list, select **Edit Game** then select the **Graphics** tab.

For a comprehensive look at how to use these settings, check out our [Understanding the graphics settings](#) guide.

All settings can also be changed in the [Configuration file](#). The configuration key is listed in italics after each setting description.

Graphics mode Changes the resolution of the game. For example, a 2x graphics mode will take a 320x200 resolution game and scale it up to 640x400.

gfx_mode

Render mode Changes how the game is rendered.

render_mode

Stretch mode Changes the way the game is displayed in relation to the window or screen size.

stretch_mode

Aspect ratio correction If ticked, corrects the aspect ratio so that games appear the same as they would on original 320x200 resolution displays.

aspect_ratio

Fullscreen mode Switches between playing games in a window, or playing them in fullscreen mode. Switch between the two by using Alt+F5 while in a game.

fullscreen



Fig. 1: The Graphics tab in the global settings

Filter graphics If ticked, uses bilinear interpolation instead of nearest neighbor resampling for the aspect ratio correction and stretch mode. It does not affect the graphics mode.

filtering

Chapter 23

Control

Use the Control tab to change settings for joysticks, game controllers, and touch screens. This tab is not always available.

From the Launcher, select **Options**, and then select the **Control** tab.

All settings can also be changed in the [Configuration file](#). The configuration key is listed in italics after each setting description.

Pointer Speed Sets the speed for the mouse pointer, when it is controlled by the keyboard or a joystick.

kbdmouse_speed

Joy deadzone Sets the deadzone for an analog joystick. A lower value will reduce the size of the deadzone.

joystick_deadzone

Show on-screen control Toggles the small on-screen keyboard icon on and off.

Touchpad mouse mode Toggles between direct mode and touchpad mode.



Fig. 1: The Control tab in the global settings

Chapter 24

Keymaps

Use the Keymaps tab to assign actions to keyboard keys or shortcuts, or to mouse or joystick buttons.

To change settings globally:

From the Launcher, select **Options**, then select the **Keymaps** tab.

To change settings for a specific game:

Highlight the game in the games list, select **Edit Game** then select the **Keymaps** tab.

All settings can also be changed in the *Configuration file*. The configuration key is listed in italics after each setting description.

Click on the button next to the desired action to add an additional key or button. Click on the dropdown expander for more options.

If all the mapped keys are not visible, hold the pointer over the button to see all the mapped keys.

Reset Resets all keymaps to default.

Reset to defaults Resets the keymaps for that action to default.

Clear mapping Clears all keymaps for that action.

24.1 Global settings

The following are the available global keymap options. Listed in italics are the configuration keywords. For more information, see the *Configuration file* page.



Fig. 1: The Keymaps tab in the global settings



Fig. 2: The Keymaps dropdown options.

24.1.1 Global

Global Main Menu *keymap_global_MENU*

Toggle mute *keymap_global_MUTE*

Quit *keymap_global_QUIT*

Open Debugger *keymap_global_DEBUGGER*

Virtual mouse up *keymap_global_VMOUSEUP*

Virtual mouse down *keymap_global_VMOUSEDOWN*

Virtual mouse left *keymap_global_VMOUSELEFT*

Virtual mouse right *keymap_global_VMOUSERIGHT*

Slow down virtual mouse *keymap_global_VMOUSESLOW*

24.1.2 Graphics

Toggle fullscreen *keymap_sdl-graphics_FULS*

Toggle mouse capture *keymap_sdl-graphics_CAPT*

Save screenshot *keymap_sdl-graphics_SCRS*

Toggle aspect ratio correction *keymap_sdl-graphics_ASPT*

Toggle linear filtered scaling *keymap_sdl-graphics_FILT*

Cycle through stretch modes *keymap_sdl-graphics_STCH*

Increase the scale factor *keymap_sdl-graphics_SCL+*

Decrease the scale factor *keymap_sdl-graphics_SCL-*

Switch to nearest neighbour scaling *keymap_sdl-graphics_FLT1*

Switch to AdvMame 2x/3x scaling *keymap_sdl-graphics_FLT2*

Switch to HQ 2x/3x scaling *keymap_sdl-graphics_FLT3*

Switch to 2XSai scaling *keymap_sdl-graphics_FLT4*

Switch to Super2xSai scaling *keymap_sdl-graphics_FLT5*

Switch to SuperEagle scaling *keymap_sdl-graphics_FLT6*

Switch to TV 2x scaling *keymap_sdl-graphics_FLT7*

Switch to DotMatrix scaling *keymap_sdl-graphics_FLT8*

24.1.3 GUI

Interact *keymap_gui_INTRCT*

Close *keymap_gui_CLOS*

Up *keymap_gui_UP*

Down *keymap_gui_DOWN*

Left *keymap_gui_LEFT*

Right *keymap_gui_RIGHT*

24.2 Game settings

The following are the available keymap game-specific keymaps options. Listed in italics are the configuration keywords. For more information, see the [Configuration file](#) page.

24.2.1 Default game keymap

Left mouse button *keymap_engine-default_LCLK*

Middle click *keymap_engine-default_MCLK*

Right click *keymap_engine-default_RCLK*

Pause *keymap_engine-default_PAUSE*

Game menu *keymap_engine-default_MENU*

Skip *keymap_engine-default_SKIP*

Skip line *keymap_engine-default_SKLI*

Predictive input dialog *keymap_engine-default_PIND*

Confirm *keymap_engine-default_RETURN*

Up *keymap_engine-default_UP*

Down *keymap_engine-default_DOWN*

Left *keymap_engine-default_LEFT*

Right *keymap_engine-default_RIGHT*

Chapter 25

Audio

Audio settings are found on four tabs:

[Audio](#) | [Volume](#) | [MIDI](#) | [MT-32](#)

To change settings globally:

From the Launcher, select **Options**, then select the applicable tab.

To change settings for a specific game:

From the Launcher, highlight the game in the games list, select **Edit Game**, and then select the applicable tab.

For a comprehensive look at how to use ScummVM's extensive audio settings, check out our [Understanding the audio settings](#) guide.

All settings can also be changed in the [Configuration file](#). The configuration key is listed in italics after each setting description.

25.1 The Audio tab

Use the Audio tab to change the sound output for games.

Preferred device (global settings) or Music device (game-specific settings) Specifies the device ScummVM uses to output audio. When set to **<default>**, ScummVM automatically chooses the most appropriate option for the played game. If set to an MT-32 or a MIDI device, or if ScummVM chooses one of these automatically, the settings on the MT-32 or MIDI tabs also apply.

music_driver

AdLib Emulator Chooses which emulator is used by ScummVM when the AdLib emulator is chosen as the **Preferred device**.

opl_driver



Fig. 1: The Audio tab in the global settings



Fig. 2: The Audio tab in the game-specific settings.

Text and Speech For games with digitized speech, this setting lets the user decide whether to play the game with speech only, subtitles only, or both.

speech_mute

subtitles

Subtitle speed Adjusts the length of time that the subtitles are displayed on screen. The lower the speed is set, the longer the subtitles are displayed.

talkspeed

25.2 The Volume tab

Use the Volume tab to set the relative volumes for various in-game sounds.




Fig. 3: The Volume tab in the game-specific settings.

Music volume Adjusts the volume of the music in the game.

music_volume

SFX volume Adjusts the volume of the sound effects in the game.

sfx_volume

Speech volume Adjusts the volume of the digitized speech in the game, if it has any.

speech_volume

Mute All Mutes all game audio.

mute

25.3 The MIDI tab

Use the MIDI tab to change the settings of General MIDI (GM) devices.

GM Device Specifies a preferred General MIDI device, which ScummVM uses if the **Preferred device** is set to **<default>** and General MIDI playback is required.

gm_device

Soundfont Specifies the path to a soundfont file, if this is required by the GM device.

soundfont

Mixed AdLib/MIDI mode Combines MIDI music with AdLib sound effects.

multi_midi

MIDI gain Adjusts the relative volume of the MIDI music. This is only supported by some music devices.

midi_gain

25.3.1 FluidSynth

Opens a new dialog, with three further tabs: [Reverb](#) | [Chorus](#) | [Misc](#)

Reverb

Reverberation, or reverb, describes the pattern of echoes and reflections that occur when a sound is heard in an enclosed closed space, such as a room or a concert hall.

Active If ticked, reverb is added to the software synthesizer output.

fluidsynth_reverb_activate




Fig. 4: The MIDI tab in the global settings.



Fig. 5: The FluidSynth dialog, reached from the MIDI tab.

Room Sets the room size, which determines how much reverb there is.

fluidsynth_reverb_roomsize

Damp Dampens higher-frequency reverb, which produces a warmer sound.

fluidsynth_reverb_damping

Width Sets the stereo spread of the reverb signal.

fluidsynth_reverb_width

Level Sets the reverb output amplitude.

fluidsynth_reverb_level

Chorus

The chorus effect thickens and colors the audio signal so that it sounds as if there are a chorus of instruments playing one part.

Active If ticked, chorus effects are added to the software synthesizer output.

fluidsynth_chorus_activate

N Sets the voice count of the chorus, in other words, how many instruments are playing one part.

fluidsynth_chorus_nr

Level Specifies the output amplitude of the chorus signal.

fluidsynth_chorus_level

Speed Sets the modulation speed of the output, in Hz.

fluidsynth_chorus_speed

Depth Specifies the modulation depth of the chorus.

fluidsynth_chorus_depth

Type Specifies the chorus modulation waveform type.

fluidsynth_chorus_waveform

Misc

Interpolation Sets the interpolation method used by the software synthesizer.

fluidsynth_misc_interpolation

25.4 The MT-32 tab

Use the MT-32 tab to change the settings of Roland MT-32 devices.




Fig. 6: The MT-32 tab in the global settings.

MT-32 Device Specifies a preferred MT-32 device, which ScummVM uses if the **Preferred device** is set to **<default>** and MT-32 playback is required.

mt32_device

True Roland MT-32 (disable GM emulation) Tells ScummVM that the MIDI device is an actual Roland MT-32, LAPC-I, CM-64, CM-32L, CM-500 or other MT-32 device. Note that this cannot be used in conjunction with the Roland GS device option.

native_mt32

Roland GS device (enable MT-32 mappings) Tells ScummVM that the MIDI device is a GS device that has an MT-32 map, such as an SC-55, SC-88 or SC-8820. Note that this cannot be used in conjunction with the True Roland MT-32 option.

enable_gs

Chapter 26

Paths

Use the Paths tab to tell ScummVM where to look for files.

To change settings globally:

From the Launcher, select **Options**, then select the **Paths** tab.

To change settings for a specific game:

Highlight the game in the games list, select **Edit Game** then select the **Paths** tab.

All settings can also be changed in the *Configuration file*. The configuration key is listed in italics after each setting description.

Save Path Sets the path to the folder in which ScummVM stores saved games. For more information on the default location of saved games, see the *Save and Load games* page, or the guide for the platform you're using.

savepath

Theme Path Sets the path to the folder in which ScummVM stores additional themes.

themepath

Extra Path Sets the path to the folder in which ScummVM will look for various extra files. These could include additional datafiles required for certain games, Soundfonts or MT-32 ROMs.

extrapath



Fig. 1: The Paths tab in the global settings

Chapter 27

Miscellaneous

Use the Misc tab to change miscellaneous settings that don't belong on any of the other tabs.

From the Launcher, select **Options**, click the > scroll arrow until the Misc tab is visible, and then select the **Misc** tab.

All settings can also be changed in the [Configuration file](#). The configuration key is listed in italics after each setting description.

Theme Changes the visual appearance of the ScummVM Launcher

gui_theme

GUI Renderer Defines how the ScummVM GUI is rendered; normal or antialiased.

gui_renderer

Autosave Adjusts the time period between autosaves. The default setting is 5 minutes.

autosave_period

GUI Language Chooses the language of the ScummVM Launcher.

gui_language

Switch the ScummVM GUI language to the game language If ticked, the Launcher language is the same as the game language.

gui_use_game_language

Use native system file browser Uses the system file browser instead of the ScummVM browser.

gui_browser_native




Fig. 1: The Misc tab in the global settings.

Chapter 28

Cloud

Use the Cloud tab to manage connected cloud storage services.

For a comprehensive look at how to use ScummVM's built-in cloud functionality, check out our [Connecting a cloud service](#) guide.

From the Launcher, select **Options**, click the > scroll arrow until the Cloud tab is visible, and then select the **Cloud** tab.

Active storage Choose from Dropbox, OneDrive, Google Drive, or Box.

After a Cloud service has been selected, further options are available:

Sync Now Manually syncs saved games with the cloud service. Saved games automatically sync on launch, after saving, and on game load.

Download game files Downloads game files from your Cloud ScummVM folder.

Disconnect Disconnects the cloud storage account. To change accounts, disconnect and connect a new account.

Note: Cloud functionality is not supported on all platforms.



Fig. 1: The Cloud tab in the global settings

Chapter 29

LAN

Use the LAN tab to control the Local Area Network (local web server).

For a comprehensive look at how to use ScummVM's built-in LAN functionality, check out our [Using the local web server](#) guide.

From the Launcher, select **Options**, click the > scroll arrow until the LAN tab is visible, and then select the **LAN** tab.

All settings can also be changed in the [Configuration file](#). The configuration key is listed in italics after each setting description.

Run server Starts the web server. When running, this displays the URL at which the web server can be accessed.

Stop server Stops the web server.

Server's port The port on which the web server is available.

local_server_port

/root/ Path Specifies the root path of the server. Any sub-directories will be accessible.

rootpath




Fig. 1: The LAN tab in the global settings

Chapter 30

Accessibility

Use the Accessibility tab to change accessibility settings.

From the Launcher, select **Options**, click the > scroll arrow until the LAN tab is visible, and then select the **LAN** tab.

All settings can also be changed in the *Configuration file*. The configuration key is listed in italics after each setting description.

Use Text to Speech Enables text to speech. As the pointer is held over any text field in the Launcher it is converted to speech. Use the dropdown list to choose from a variety of voices.

tts_enabled




Fig. 1: The Accessibility tab in the global settings.

Chapter 31

Command line interface

Launching ScummVM from the command line lets you pass a number of options, some of which override the applicable global or game-specific settings. It also lets you launch straight into a game without going to the Launcher first.

Some options, such as `--help` or `--list-audio-devices`, allow you to view information about ScummVM directly on the command line without starting the Launcher or starting a game.

31.1 Usage

```
scummvm [option] [game]
```

To launch ScummVM, enter the path to ScummVM. Optionally, follow this with any of the options documented below, and/or the path to the game you wish to start. If a game has already been added to the games list in the Launcher, you can pass the game id instead of the path to the game.

Windows

The following examples assume that the path to ScummVM is `C:\Program Files\ScummVM\scummvm.exe`.

To run Monkey Island, fullscreen (`-f`):

```
C:\Program Files\ScummVM\scummvm.exe -f monkey
```

To run Full Throttle, fullscreen (`-f`) and with subtitles enabled (`-n`), specifying the path to the game on a CD (`-p`):

```
C:\Program Files\ScummVM\scummvm.exe -f -n -pD:``resource``ft
```

macOS

The following examples assume the path to the ScummVM app is Applications/ScummVM.app.

If you are unsure of the path to the app, drag the ScummVM app icon into the Terminal window. This prints the path to the ScummVM app.

To run ScummVM from the command line, add /Contents/MacOS/scummvm to that path.

To run Monkey Island, fullscreen (-f):

```
/Applications/ScummVM.app/Contents/MacOS/scummvm -f monkey
```

To run Full Throttle, fullscreen (-f) and with subtitles enabled (-n), specifying the path to the game on a CD (-p):

```
/Applications/ScummVM.app/Contents/MacOS/scummvm -f -n -p/cdrom/resource/ft
```

Linux

The following examples assume the path to ScummVM is /usr/games/scummvm.

To run Monkey Island, fullscreen (-f):

```
/usr/games/scummvm -f monkey
```

To run Full Throttle, fullscreen (-f) and with subtitles enabled (-n), specifying the path to the game on a CD (-p):

```
/usr/games/scummvm -f -n -p/cdrom/resource/ft
```

Tip: If ScummVM is on PATH, there is no need to enter the full path to ScummVM. Similarly, if a game is already added to the Launcher, there is no need to specify the path to the game.

31.2 Options

The meaning of most options can be inverted by prefixing them with no-. For example, --no-aspect-ratio will turn aspect ratio correction off. This does not apply to short options.

Option parameters are shown below in capitals, and need to be replaced with real values.

Short options are listed where they are available.

Option	Short	Description
--add	-a	Adds all games from current or specified directory. If --game=NAME is passed, only the game with id NAME is added. See also --detect. Use --path=PATH before -a or --add to specify a directory.
--alt-intro		<i>Uses alternative intro for CD versions</i>
--aspect-ratio		<i>Enables aspect ratio correction</i>
--auto-detect		Displays a list of games from the current or specified directory and starts the first game. Use --path=PATH before --auto-detect to specify a directory.
--boot-param=NUM	-b	Pass number to the boot script (boot param).
--cdrom=DRIVE		Sets the CD drive to play CD audio from. This can be a drive, path, or numeric index (default: 0)
--config=FILE	-c	Uses alternate configuration file
--console		Enables the console window (default: enabled). Win32 and Symbian32 only.
--copy-protection		Enables copy protection
--debug-channels-only		Shows only the specified debug channels
--debugflags=FLAGS		Enables engine specific debug flags
--debuglevel=NUM	-d	Sets debug verbosity level
--demo-mode		Starts demo mode of Maniac Mansion or The 7th Guest
--detect		Displays a list of games with their game id from the current or specified directory. This does not add the game to the games list. Use --path=PATH before --detect to specify a directory.
--dimuse-tempo=NUM		Sets internal Digital iMuse tempo (10 - 100) per second (default: 10)
--engine-speed=NUM		Sets frames per second limit (0 - 100) for Grim Fandango or Escape from Monkey Island (default: 60).
--dump-scripts	-u	Enables script dumping if a directory called 'dumps' exists in the current directory
--enable-gs		<i>Enables Roland GS mode for MIDI playback</i>
--extrapath=PATH		<i>Extra path to additional game data</i>
--filtering		<i>Forces filtered graphics mode</i>
--fullscreen	-f	<i>Forces full-screen mode</i>
--game=NAME		In combination with --add or --detect only adds or attempts to detect the <i>game with id NAME</i> .
--gfx-mode	-g	<i>Selects graphics mode</i>
--gui-theme=THEME		<i>Selects GUI theme</i>
--help	-h	Displays a brief help text and exit
--joystick=NUM		Enables joystick input (default: 0 = first joystick)
--language	-q	<i>Selects language</i> (en, de, fr, it, pt, es, jp, zh, kr, se, gb, hb, ru, cz)
--list-audio-devices		Lists all available audio devices

continues on next page

Table 1 – continued from previous page

Option	Short	Description
--list-saves --game=TARGET		Displays a list of saved games for the game (TARGET) specified
--list-targets	-t	Displays list of configured targets and exits
--list-themes		Displays list of all usable GUI themes
--logfile=PATH	-l	Uses alternate path for log file (SDL backend only).
--midi-gain=NUM		<i>Sets the gain for MIDI playback.</i> 0-1000 (default: 100). Only supported by some MIDI drivers
--multi-midi		<i>Enables combination AdLib and native MIDI</i>
--music-driver=MODE	-e	<i>Selects preferred music device</i>
--music-volume=NUM	-m	<i>Sets the music volume,</i> 0-255 (default: 192)
--native-mt32		<i>True Roland MT-32 (disables GM emulation)</i>
--no-filtering		Forces unfiltered graphics mode
--no-fullscreen	-F	Forces windowed mode
--opl-driver=DRIVER		<i>Selects AdLib (OPL) emulator</i>
--output-rate=RATE		Selects output sample rate in Hz
--path=PATH	-p	Sets path to where the game is installed
--platform=STRING		<i>Specifies platform of game.</i> Allowed values: 2gs, 3do, acorn, amiga, atari, c64, fmtowns, nes, mac, pc pc98, pce, segacd, wii, windows.
--recursive		In combination with --add or ``--detect recurses down all subdirectories
--render-mode=MODE		<i>Enables additional render modes</i>
--save-slot=NUM	-x	Specifies the saved game slot to load (default: autosave)
--savepath=PATH		<i>Specifies path to where saved games are stored</i>
--sfx-volume=NUM	-s	<i>Sets the sfx volume,</i> 0-255 (default: 192)
--soundfont=FILE		<i>Selects the SoundFont for MIDI playback..</i> Only supported by some MIDI drivers.
--speech-volume=NUM	-r	<i>Sets the speech volume,</i> 0-255 (default: 192)
--subtitles	-n	<i>Enables subtitles</i>
--talkspeed=NUM		<i>Sets talk speed for games</i> (default: 60)
--tempo=NUM		Sets music tempo (in percent, 50-200) for SCUMM games (default: 100)
--themepath=PATH		<i>Specifies path to where GUI themes are stored</i>
--version	-v	Displays ScummVM version information and exits

Chapter 32

Configuration file

The configuration file provides a way to edit both global and game-specific settings. It is a text file containing configuration keys and parameters.

Settings are also accessible directly from the Launcher. See [Changing settings](#).

32.1 Location

The configuration file saves to different default locations, depending on the platform.

Windows

95/98/ME

C:\WINDOWS\scummvm.ini

Windows NT4

C:\WINDOWS\Profiles\username\Application Data\ScummVM\scummvm.ini

Windows 2000/XP

\Documents and Settings\username\Application Data\ScummVM\scummvm.ini

Window Vista/7/8/10

%APPDATA%\ScummVM\scummvm.ini

macOS

~/Library/Preferences/ScummVM Preferences

Note: If an earlier version of ScummVM was installed on your system, the configuration file remains in the previous default location of ~/.scummvmrc.

Tip: To see the Library folder, press Option when clicking **Go** in the Finder menu.

Linux

ScummVM follows the XDG Base Directory Specification, so by default the configuration file is found at ~/.config/scummvm/scummvm.ini, but its location might vary depending on the value of the XDG_CONFIG_HOME environment variable.

If ScummVM was installed using Snap, the configuration file is found at ~/snap/scummvm/current/.config/scummvm/scummvm.ini

Note: .config is a hidden directory. To view it use `ls -a` on the command line.

32.2 Using the configuration file

Global settings are listed under the [scummvm] heading. Global *keymaps settings* are listed under the [keymapper] heading. Game-specific settings, including keymaps, are listed under the heading for that game, for example [queen] for Flight of the Amazon Queen. Use the configuration keys to change settings.

32.2.1 Example of a configuration file

```
[scummvm]
gfx_mode=supereagle
fullscreen=true
savepath=C:\saves\

[sky]
path=C:\games\SteelSky\

[germansky]
gameid=sky
language=de
path=C:\games\SteelSky\
```

(continues on next page)

(continued from previous page)

```
description=Beneath a Steel Sky w/ German subtitles
```

```
[germandott]
gameid=tentacle
path=C:\german\tentacle\
description=German version of DOTT
```

```
[tentacle]
path=C:\tentacle\
subtitles=true
music_volume=40
sfx_volume=255
```

```
[loomcd]
cdrom=1
path=C:\loom\
talkspeed=5
savepath=C:\loom\saves\
```

```
[monkey2]
path=C:\amiga_mi2\
music_driver=windows
```

32.3 Configuration keys

There are many recognized configuration keys. In the table below, each key is either linked to an explanatory description in the Settings pages, or has further information in the **Description/Options** column.

Key	Type	Default	Description/Options
<code>alsa_port</code>	integer		Specifies which ALSA port ScummVM uses when using the ALSA music driver (Linux).
<code>alt_intro</code>	boolean	false	
<code>altamigapalette</code>	boolean	false	
<code>apple2gs_speedmenu</code>	boolean	false	
<code>aspect_ratio</code>	boolean	false	

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>audio_buffer_size</i>	integer	Calculated based on output sampling frequency to keep audio latency below 45ms.	Overrides the size of the audio buffer. Allowed values: <ul style="list-style-type: none"> • 256 • 512 • 1024 • 2048 • 4096 • 8192 • 16384 • 32768
<i>autosave_period</i>	integer	300	
auto_savenames	boolean	false	Automatically generates names for saved games
<i>bilinear_filtering</i>	boolean	false	
boot_param	integer	none	
<i>bright_palette</i>	boolean	true	
cdrom	integer	0	Sets which CD drive to play CD audio from (as a numeric index). If a negative number is set, ScummVM does not access the CD drive.
<i>color</i>	boolean		
<i>commandpromptwindow</i>	boolean	false	
confirm_exit	boolean	false	ScummVM requests confirmation before quitting (SDL backend only)
console	boolean	true	Enables the console window for Win32/Symbian32.
controller_map_db	string	gamecontrollerdb.txt is loaded from the specified extrapath	Specifies the custom controller mapping file to load to complete the default database (SDL backend only).
copy_protection	boolean	false	Enables copy protection

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
demo_mode	boolean	false	Starts demo mode of Maniac Mansion or the 7th Guest
<i>description</i>	string		
desired_screen_aspect_ratio	string	auto	
dimuse_tempo	integer	10	Sets internal Digital iMuse tempo per second; 0 - 100
<i>disable_dithering</i>	boolean	false	
<i>disable_stamina_drain</i>	boolean	false	
<i>DurableArmor</i>	boolean	false	
<i>EasyMouse</i>	boolean	true	
<i>enable_black_lined_video</i>		false	
<i>enable_censoring</i>	boolean	false	
<i>enable_color_blind</i>	boolean	false	
<i>enable_gore</i>	boolean		
<i>enable_gs</i>	boolean		
<i>enable_high_resolution_graphics</i>	boolean	true	
<i>enable_hq_video</i>	boolean	true	
<i>enable_larryscale</i>	boolean	true	
<i>enable_reporter</i>	boolean	false	RISC OS only.
<i>enable_video_upscale</i>	boolean	true	
<i>enable_tts</i>	boolean	false	
enable_unsupported_game_warning	boolean	true	Shows a warning when adding a game that is unsupported.
extra	string		Shows additional information about a game, such as version
<i>extrapath</i>	string	None	
<i>fade_style</i>	boolean	true	
<i>filtering</i>	boolean	false	
<i>floating_cursors</i>	boolean	false	
<i>fluidsynth_chorus_activate</i>	boolean	true	
<i>fluidsynth_chorus_depth</i>	integer	80	<ul style="list-style-type: none"> • 0 - 210
<i>fluidsynth_chorus_level</i>	integer	100	<ul style="list-style-type: none"> • 0 - 100
<i>fluidsynth_chorus_nr</i>	integer	3	<ul style="list-style-type: none"> • 0 - 99

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>fluidsynth_chorus_speed</i>	integer	30	<ul style="list-style-type: none"> • 10 - 500
<i>fluidsynth_chorus_waveform</i>	string	Sine	<ul style="list-style-type: none"> • sine • triangle
<i>fluidsynth_misc_interpolation</i>	string	4th	<ul style="list-style-type: none"> • none • 4th • 7th • linear.
<i>fluidsynth_reverb_activate</i>	boolean	true	
<i>fluidsynth_reverb_damping</i>	integer	0	<ul style="list-style-type: none"> • 0 - 1
<i>fluidsynth_reverb_level</i>	integer	90	<ul style="list-style-type: none"> • 0 - 100
<i>fluidsynth_reverb_roomsize</i>	integer	20	<ul style="list-style-type: none"> • 0 - 100
<i>fluidsynth_reverb_width</i>	integer	1	<ul style="list-style-type: none"> • 0 - 100
<i>frames_per_secondfl</i>	boolean	false	
<i>frontpanel_touchpad_mode</i>	boolean	false	
<i>fullscreen</i>	boolean	false	
<i>gameid</i>	string		
<i>gamepath</i>	string		Specifies the path to the game

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>gfx_mode</i>	string	normal (1x)	<ul style="list-style-type: none"> • 1x • 2x • 3x • 2xsai • super2xsai • supereagle • advmame2x • advmame3x • hq2x • hq3x • tv2x • dot-matrix • opengl
<i>gm_device</i>	string	null	<ul style="list-style-type: none"> • auto • alsa • seq • sndio • fluidsynth • timidity
<i>GraphicsDithering</i>	boolean	true	
<i>gui_browser_native</i>	boolean	true	
<i>gui_browser_show_hidden</i>	boolean	false	Shows hidden files/folders in the ScummVM file browser.
<i>gui_list_max_scan_entries</i>	integer	-1	Specifies the threshold for scanning directories in the Launcher. If the number of game entires exceeds the specified number, then scanning is skipped.
<i>gui_saveload_chooser</i>	string	grid	<ul style="list-style-type: none"> • list • grid
<i>gui_saveload_last_pos</i>	string	0	
<i>gui_use_game_language</i>	boolean		
<i>helium_mode</i>	boolean	false	

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>help_style</i>	boolean	false	
<i>herculesfont</i>	boolean	false	
<i>hpbargraphs</i>	boolean	true	
<i>hypercheat</i>	boolean	false	
<i>iconpath</i>	string		Specifies the path to icons to use as overlay for the ScummVM icon in the Windows taskbar or the macOS Dock when running a game. The icon files should be named after the <i>gameid</i> , and be an ICO file on Windows, or a PNG file on macOS.
<i>improved</i>	boolean	true	
<i>InvObjectsAnimated</i>	boolean	true	
<i>joystick_deadzone</i>	integer	3	
<i>joystick_num</i>	integer	0	Enables joystick input and selects which joystick to use. The default is the first joystick.
<i>kbdmouse_speed</i>	integer	10	
<i>keymap_engine-default_DOWN</i>	string	JOY_DOWN	
<i>keymap_engine-default_LCLK</i>	string	MOUSE_LEFT JOY_A	
<i>keymap_engine-default_LEFT</i>	string	JOY_LEFT	
<i>keymap_engine-default_MCLK</i>	string	MOUSE_MIDDLE	
<i>keymap_engine-default_MENU</i>	string	F5 JOY_LEFT_SHOULDER	
<i>keymap_engine-default_PAUSE</i>	string	SPACE	
<i>keymap_engine-default_PIND</i>	string		
<i>keymap_engine-default_RCLK</i>	string	MOUSE_RIGHT JOY_B	
<i>keymap_engine-default_RETURN</i>	string	RETURN	
<i>keymap_engine-default_RIGHT</i>	string	JOY_RIGHT	
<i>keymap_engine-default_SKIP</i>	string	ESCAPE JOY	
<i>keymap_engine-default_SKLI</i>	string	PERIOD JOY_X	
<i>keymap_engine-default_UP</i>	string	JOY_UP	
<i>keymap_global_DEBUGGER</i>	string	C+A+d	
<i>keymap_global_MENU</i>	string	C+F5 JOY_START	
<i>keymap_global_MUTE</i>	string	C+u	
<i>keymap_global_QUIT</i>	string	C+q	

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>keymap_global_VMOUSEDOWN</i>	string	JOY_LEFT_STICK_Y+	
<i>keymap_global_VMOUSELEFT</i>	string	JOY_LEFT_STICK_X-	
<i>keymap_global_VMOUSERIGHT</i>	string	JOY_LEFT_STICK_X+	
<i>keymap_global_VMOUSESLOW</i>	string	JOY_RIGHT_SHOULDER	
<i>keymap_global_VMOUSEUP</i>	string	JOY_LEFT_STICK_Y-	
<i>keymap_gui_CLOS</i>	string	ESCAPE JOY_Y	
<i>keymap_gui_DOWN</i>	string	JOY_DOWN	
<i>keymap_gui_INTRCT</i>	string	JOY_A	
<i>keymap_gui_LEFT</i>	string		
<i>keymap_gui_RIGHT</i>	string	JOY_RIGHT	
<i>keymap_gui_UP</i>	string	JOY_UP	
<i>keymap_sdl-graphics_ASPT</i>	string	C+A+a	
<i>keymap_sdl-graphics_CAPT</i>	string	C+m	
<i>keymap_sdl-graphics_FILT</i>	string	C+A+f	
<i>keymap_sdl-graphics_FLT1</i>	string	C+A+1	
<i>keymap_sdl-graphics_FLT2</i>	string	C+A+2	
<i>keymap_sdl-graphics_FLT3</i>	string	C+A+3	
<i>keymap_sdl-graphics_FLT4</i>	string	C+A+4	
<i>keymap_sdl-graphics_FLT5</i>	string	C+A+5	
<i>keymap_sdl-graphics_FLT6</i>	string	C+A+6	
<i>keymap_sdl-graphics_FLT7</i>	string	C+A+7	
<i>keymap_sdl-graphics_FLT8</i>	string	C+A+8	
<i>keymap_sdl-graphics_FULS</i>	string	A+RETURN	
<i>keymap_sdl-graphics_SCL-</i>	string	C+A+MINUS	
<i>keymap_sdl-graphics_SCL+</i>	string	C+A+PLUS	
<i>keymap_sdl-graphics_SCRS</i>	string	A+s	
<i>keymap_sdl-graphics_STCH</i>	string	C+A+s	
<i>language</i>	string		
<i>local_server_port</i>	integer	12345	
<i>midi_gain</i>	integer		<ul style="list-style-type: none"> • 0 - 1000
<i>mm_nes_classic_palette</i>	boolean	false	
<i>monotext</i>	boolean	true	
<i>mousebtswap</i>	boolean	false	
<i>mousesupport</i>	boolean	true	
<i>mt32_device</i>	string	auto	<ul style="list-style-type: none"> • auto • alsa • seq • fluidsynth • mt32 • timidity

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>multi_midi</i>	boolean		
<i>music_driver</i> [scummvm]	string	auto	<ul style="list-style-type: none"> • null • auto • seq (Unix) • sndio (Unix) • alsa (Unix) • CAMD (Amiga) • core (Mac) • coremidi (Mac - hardware) • windows (Windows) • fluidsynth • mt32 • adlib • pcspk • pcjr • cms • timidity
<i>music_driver</i> [game]	string	auto	<p>The same options as <i>music_driver</i> in [scummvm] plus:</p> <ul style="list-style-type: none"> • towns • C64 • pc98 • segacd
<i>music_mute</i>	boolean	false	Mutes the game music.
<i>music_volume</i>	integer	192	<ul style="list-style-type: none"> • 0-256
<i>mute</i>	boolean	false	
<i>native_fb01</i>	boolean	false	
<i>native_mt32</i>	boolean	false	
<i>NaughtyMode</i>	boolean	true	
<i>nodelaymillisfl</i>	boolean	false	
<i>ntsc</i>	boolean		
<i>object_labels</i>	boolean	true	
<i>opl2lpt_parport</i>		null	

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>opl_driver</i>	string		<ul style="list-style-type: none"> • auto • mame • db • nuked • alsa • op2lpt • op3lpt
<i>originalsaveload</i>	boolean	false	
<i>output_rate</i>	integer		Sensible values are: <ul style="list-style-type: none"> • 11025 • 22050 • 44100
<i>platform</i>	string		
<i>portaits_on</i>	boolean	true	
<i>prefer_digitalsfx</i>	boolean	true	
<i>render_mode</i>	string	default	<ul style="list-style-type: none"> • hercGreen • hercAmber • cga • ega • vga • amiga • fmtowns • pc9821 • pc9801 • 2gs • atari • macintosh
<i>rootpath</i>	string		
<i>savepath</i>	string		
<i>save_slot</i>	integer	autosave	Specifies the saved game slot to load
<i>scalemakingofvideos</i>	boolean	false	
<i>scanlines</i>	boolean	false	
<i>screenshotpath</i>	string		Specifies where screenshots are saved
<i>sfx_mute</i>	boolean	false	Mutes the game sound effects.
<i>sfx_volume</i>	integer	192	
<i>shorty</i>	boolean	false	

continues on next page

Table 1 – continued from previous page

Key	Type	Default	Description/Options
<i>show_fps</i>	boolean	false	
<i>ShowItemCosts</i>	boolean	false	
<i>silver_cursors</i>	boolean	false	
<i>sitcom</i>	boolean	false	
<i>skip_support</i>	boolean	true	
<i>skiphalloffrecordsscenes</i>	boolean	false	
<i>smooth_scrolling</i>	boolean	true	
<i>speech_mute</i>	boolean	false	
<i>speech_volume</i>	integer	192	
<i>stretch_mode</i>	string		<ul style="list-style-type: none"> • center • pixel-perfect • fit • stretch • fit_force_aspect
<i>studio_audience</i>	boolean	true	
<i>subtitles</i>	boolean	false	
<i>talkspeed</i>	integer	60	<ul style="list-style-type: none"> • 0 - 255
tempo	integer	100	Sets the music tempo, in percent, for SCUMM games. <ul style="list-style-type: none"> • 50-200
<i>TextWindowAnimated</i>	boolean	true	
<i>themepath</i>	string	none	
<i>transparent_windows</i>	boolean	true	
<i>transparentdialogboxes</i>	boolean	false	
<i>tts_enabled</i>	boolean	false	
<i>tts_narrator</i>	boolean	false	
<i>use_cdaudio</i>	boolean	true	If true, ScummVM uses audio from the game CD.
versioninfo	string		Shows the ScummVM version that created the configuration file.
<i>window_style</i>	boolean	true	
<i>windows_cursors</i>	boolean	false	

Chapter 33

Understanding the audio settings

This guide expands on the information contained on the [audio settings](#) page.

33.1 How do the audio settings work together?

The **Preferred device** in the global settings Audio tab, or the **Music device** in the game-specific settings Audio tab, specifies the device that ScummVM uses to output audio. This device can be an emulated sound device or a software synthesizer, or an actual hardware device such as a soundcard or a hardware MIDI synthesizer. When set to **<default>**, ScummVM will automatically choose the most appropriate option for the played game.

If **Preferred device** or **Music device** is set to **<default>** and ScummVM chooses either an MT-32 or General MIDI device automatically, the settings on the MT-32 or MIDI tabs also apply, and the devices selected on these tabs are the ones that will be used. If **Preferred device** or **Music device** is set to either an MT-32 device or a GM device, ScummVM will use that device and ignore the devices chosen on the MT-32 and MIDI tabs.

Not all settings are applicable to all games. For example, changing the General MIDI settings will not have any effect on a game that only has CD audio.

33.2 The evolution of PC audio

For a look at the evolution of PC audio, see [this video on YouTube](#), or [this excellent post](#).

Many of these old-school audio devices can be emulated by ScummVM:

- PC Speaker: emulates the built-in PC speaker. This is mostly supported by older games, and was the only option before sound cards became widely used.

pcspk

- IBM PCjr: emulates the sound of the 1984 IBM PCjr computer, which, enhanced with a Texas Instruments chip, provided three-voice sound and a white noise generator.

pcjr

- Creative Music System ([C/MS](#)): emulates the first sound card developed by Creative Technology (later Creative Labs), the precursor to the SoundBlaster line of sound cards. The C/MS provided 12 channels of square-wave stereo sound.

cms

- C64 Audio: emulates the sound chip ([Sound Interface Device](#)) in the Commodore 64 computer. The SID was a three-voice synthesizer module, with a fourth voice for sampled drums or speech.

C64

- Amiga Audio: emulates the Amiga audio chip, [Paula](#), which had four 8-bit PCM sound channels.

CAMD

- FM-Towns Audio: emulates the audio of the [FM Towns PC](#). Games on FM Towns computers often used audio CD standard tracks. The soundchips were capable of eight PCM voices and six FM channels.

towns

- PC-98 Audio: emulates the audio of the NEC PC-9801-26 and PC-9801-86 sound cards.

pc98

- SegaCD Audio: emulates the audio of the Sega CD add-on for the Sega Genesis/32x.

segacd

To find out which emulation is compatible with the game you're playing, have a look at the manual that comes with the game.

33.3 What is MIDI?

MIDI is a communications protocol for musical information; it can be likened to digital sheet music. By itself, MIDI is not sound. Hardware or software synthesizers create (synthesize) audio by interpreting the information given to them by the MIDI protocol.

While some older soundcards (and a few modern ones) have their own hardware-based synthesizers, this is relatively rare. Generally, soundcard drivers work with software synthesizers to interpret MIDI and output audio.

Some games only contain MIDI audio data. In the past this prevented audio for these games from working on platforms that did not support MIDI, or with soundcards that did not provide MIDI drivers. ScummVM can now convert MIDI data to sampled audio using MIDI device emulators.

33.3.1 What is General MIDI?

General MIDI is a MIDI standard which is implemented by a large number of devices. While using MIDI as its protocol, it also specifies an instrument map and some other information that devices must implement.

General MIDI device emulation (FluidSynth)

If the ScummVM you're using has libfluidsynth support it will be able to play MIDI music by using the FluidSynth emulator if set as the **Preferred device** or **Music device**, or if specified in the MIDI tab when **Preferred device** or **Music device** is set to **<default>** and ScummVM chooses General MIDI output automatically.

You will have to specify a SoundFont in the MIDI tab for ScummVM to use FluidSynth. MIDI is like digital sheet music; it needs a library of sound samples known as a SoundFont to draw from to synthesize music. See the [ScummVM forum](#) for an example of a great SoundFont.

The default output volume from FluidSynth can be fairly low, so ScummVM automatically sets the gain to get a stronger signal. Use the [MIDI gain](#) setting to further adjust this.

The processor requirements for FluidSynth are quite high; a fast CPU is recommended.

33.3.2 What is MT-32?

The MT-32 is a [Roland sound module](#), although the term also commonly refers to a range of devices that are fully compatible with the MT-32. MT-32 devices also use MIDI as the communications protocol.

MT-32 device emulation

Some games which contain MIDI music data have tracks designed specifically for the Roland MT-32. ScummVM can emulate the MT-32 device, however you must provide the original MT-32 ROMs, taken from the MT-32 module, for the emulator to work. These files are:

- MT32_PCM.ROM - IC21 (512KB)
- MT32_CONTROL.ROM - IC26 (32KB) and IC27 (32KB)

Place these ROMs in the game directory, in your extrapath, or in the directory where your ScummVM executable resides. ScummVM also looks for CM32L_PCM.ROM and CM32L_CONTROL.ROM—the ROMs from the CM-32L device—and uses these instead of the MT32 ROMs if they are available.

Note: The MT-32 ROMs are copyrighted, and are not provided by ScummVM. These must be taken from your own MT-32 module.

ScummVM uses the MT-32 emulator if it is set as the **Preferred device** or **Music device**, or if it is specified in the MT-32 tab when **Preferred device** or **Music device** is set to **<default>** and ScummVM chooses MT-32 output automatically.

You don't need to enable **True Roland MT-32** in the MT-32 tab, ScummVM does this automatically.

Tip: Some games work better with some MT-32 devices than others. As an example, Lure of the Temptress makes use of extra sound effects included with the CM-32L and won't sound right with an MT-32. Likewise, The Colonel's Bequest uses some bugs in the early MT-32 modules, which means that later devices will play incorrect sound effects!

[This Wikipedia article](#) provides a comprehensive list of MT-32 compatible games, including which games work best with which device.

The processor requirements for the MT-32 emulator are quite high; a fast CPU is strongly recommended.

33.3.3 Built-in MIDI support

All MIDI ports show up in the **Preferred device** or **Music device** dropdown selector. If you have selected a MIDI port, you need to specify what type of MIDI device this is with the options in the *MT-32* tab.

- Enable **True Roland MT-32** to tell ScummVM that the MIDI device is an MT-32 (or fully compatible) device.
- Enable **Roland GS device** to tell ScummVM to use an MT-32 soundtrack on a GS device. This is not supported by all games.
- If no options are selected, ScummVM treats the device on the port as a General MIDI device.

If you select an option that does not match the actual device, this might have unintended consequences. For example, if a game only has support for MT-32 and you have a General MIDI device selected as the **Preferred device** or **Music device**, ScummVM will convert the MT-32 MIDI data to GM-compatible MIDI data. While this might work fine for some games, it really depends on how the game has made use of the MT-32.

macOS/Mac OSX

Mac has a built-in MIDI synthesizer; Apple DLS software synthesizer. It uses the Mac's built-in sounds (which are based on Roland GS).

The [Apple Support page](#) has further information about setting up MIDI devices on a Mac.

Windows

Windows has a generic built-in MIDI synthesizer—GS WaveTable Synth—also based on Roland’s GS sounds.

For an in-depth look at audio and MIDI device setup on a Windows computer, see this [very helpful article](#).

Linux

MIDI device setup might vary depending on your Linux distro.

If you do not have a hardware MIDI device, there are two options: FluidSynth and TiMidity. FluidSynth is recommended as TiMidity might have some lag, depending on the system.

Here are a couple of helpful articles from the Ubuntu community documentation to get you started.

[How to: Software Synthesizers](#)

[How to: Hardware synthesizer soundcard setup](#)

33.4 What is AdLib?

AdLib devices do not use MIDI. They instead have a chip that produces sound through FM synthesis. While some games do store their audio data using a MIDI-derived format, this is converted by the game to work with the AdLib chip. ScummVM emulates a few different AdLib configurations, and selects the most appropriate for the game:

- The original AdLib and SoundBlaster card had one OPL2 chip.
- The SoundBlaster Pro 1 had two OPL2 chips
- The SoundBlaster Pro 2 and 16 had an OPL3 chip.

The AdLib emulator setting offers MAME, DOSBox and Nuked emulation, with MAME being the least accurate and using the least CPU power, and Nuked being the most accurate and also using the most CPU power - DOSBox is somewhere in between.

There is also the option to select the OPL2LPT and OPL3LPT devices, which are external hardware devices with a real OPL chip, connected through the parallel port of a computer.

AdLib does not require a SoundFont or ROMs, so for many games it might be the easiest to configure. However, if an MT-32 or GS emulator or device is available, ScummVM will prioritize this over AdLib.

33.4.1 Mixed AdLib/MIDI mode

Some games contain sound effects that are exclusive to the AdLib soundtrack, or the AdLib soundtrack might provide better sound effects. For these games, you can combine MIDI music with AdLib sound effects by using the *mixed AdLib/MIDI mode*.

Note: Mixed AdLib/MIDI mode is not supported by all games.

33.5 Digital Sound effects

Some games have both sampled and synthesized sound effects. ScummVM will usually use the sampled sound effects, even if you select Adlib, MT-32 or GM as your audio device. Some games allow you to choose between sampled and synthesized sound effects by using the **Prefer digital sound effects** option in the Engine tab.

33.6 Sample output rate

The output sample rate tells ScummVM how many sound samples to play per channel per second.

Most of the sounds were originally sampled at either 22050Hz or 11025Hz, so using a higher sample rate in these cases will not improve the quality of the audio.

For games that use CD audio, the sounds were probably sampled at 44100Hz, so that is a better sample rate to choose for these games.

ScummVM generates the samples when using AdLib, FM-Towns, PC Speaker or IBM PCjr emulated sound. 22050Hz will usually be fine for these options, although for Beneath a Steel Sky 44100Hz is recommended.

ScummVM has to resample all sounds to the selected output frequency. It is recommended to choose an output frequency that is a multiple of the original frequency. Choosing an in-between number might not be supported by your sound card.

33.7 Audio buffer size

There is no option to control audio buffer size through the GUI, but the default value can be overridden in the *configuration file* with the *audio_buffer_size* configuration keyword. The default value is calculated based on output sampling frequency to keep audio latency below 45ms.

Appropriate values are normally between 512 and 8192, but the value must be one of: 256, 512, 1024, 2048, 4096, 8192, 16384, or 32768.

Smaller values yield faster response time, but can lead to stuttering if your CPU isn't able to catch up with audio sampling when using the sound emulators. Large buffer sizes might lead to minor audio delays (high latency).

Chapter 34

Understanding the graphics settings

This guide expands on the information contained on the [graphics settings](#) page.

34.1 How do the graphics settings work together?

The graphics mode, aspect ratio, and stretch mode settings work together to change the resolution and display of each game. The first setting applied to the image is the graphics mode, then the aspect ratio correction, and then the stretch mode setting. The only exception to this is OpenGL mode, which applies all settings in one pass to arrive at a final image.

Render modes are only applicable to some older games that were designed to be played on multiple systems, and lets us choose which system's graphics to replicate.

34.2 Graphics modes

The original game graphics are upscaled using different graphical filters, which are specialized algorithms used to ensure that low resolution pixel-art still looks good when it is displayed at a higher resolution.

If the game originally ran at a resolution of 320x200—which is typical for most SCUMM games—then using a graphics mode with a scale factor of 2x yields 640x400 graphics. A 3x scale factor yields 960x600.

There is always a speed penalty when using any form of filtering.

34.2.1 A comparison of graphics modes



Fig. 1: **1x**: No filtering, no scaling. Fastest.



Fig. 2: **2x**: No filtering, scales the image by a factor of 2. Default for non 640x480 games.



Fig. 3: **3x**: No filtering, scales the image by a factor of 3.

Note: Not all platforms support all the graphics modes.

To switch between graphics modes, press Ctrl + Alt and 1 to 8.



Fig. 4: **2xSAI**: SAI filter, factor 2x.



Fig. 5: **Super2xSAI**: Enhanced 2xSAI filtering, factor 2x.



Fig. 6: **SuperEagle**: Less blurry than 2xSAI, but slower. Factor 2x.



Fig. 7: **AdvMAME2x**: Doesn't rely on blurring like 2xSAI, fast. Factor 2x.



Fig. 8: **AdvMAME3x**: Doesn't rely on blurring like 2xSAI, fast. Factor 3x.



Fig. 9: **HQ2x**: Very nice high quality filter, but slow. Uses lookup tables to create anti-aliased output. Factor 2x.



Fig. 10: **HQ3x**: Very nice high quality filter, but slow. Uses lookup tables to create anti-aliased output. Factor 3x.



Fig. 11: **TV2x**: Interlace filter. Introduces scan lines to emulate a TV. Factor 2x.



Fig. 12: **DotMatrix**: Dot matrix effect. Factor 2x.

34.2.2 OpenGL mode

OpenGL graphics mode works a little differently to the other graphics modes. Instead of applying the aspect ratio and stretch mode settings one after the other (and after the graphics mode scaling has been applied), it does all the scaling and stretching in one step, going directly from the original game resolution to the final display resolution. OpenGL mode uses hardware rendering, instead of software rendering.

Output is controlled by your window size (or screen resolution if in full screen) and the stretch mode selected, as well as the **Filter graphics** option.

34.3 Aspect ratio correction

Older games were designed to be run at 320x200 pixels, but on systems where each pixel was rectangular instead of square. This means that on modern systems these games look wider and flatter than they are supposed to. Aspect ratio correction duplicates lines of pixels to correct this.

For a game with an original resolution of 320x200, aspect ratio correction results in a resolution of 320x240.

To toggle aspect ratio on and off, press **Ctrl+Alt+a**.



Fig. 13: No aspect ratio correction applied.

34.4 Stretch modes

There are five stretch modes:

- Center: centers the image in the window.
- Pixel-perfect scaling: scales the image to the highest multiple of the game resolution that fits the window, or that fits the screen if in fullscreen mode. Any empty space is filled with black bars.
 - For example, a game with an original resolution of 320x200 with aspect ratio correction applied (320x240) and a 3x graphics mode, will be stretched to a multiple of 900x720 pixels: 1800x1440, 2700x2160 and so on.
- Fit to window: fits the image to the window, but maintains the aspect ratio and does not stretch it to fill the window.
- Stretch: stretches the image to fill the window
- Fit to window (4:3): fits the image to the window, at a forced 4:3 aspect ratio.

To switch between stretch modes, press `Ctrl+Alt+s`.



Fig. 14: Aspect ratio correction applied. The moon is actually round, as it should be!

34.5 Render mode

For most games this setting will have no effect. For some of the older games that could be played on different systems and graphics cards, this control lets you decide which system you want ScummVM to reproduce.

Below are some of the common render modes, to illustrate how the render mode setting works.



Fig. 15: Maniac Mansion with <default> render mode

34.6 Filter graphics

When enabled, ScummVM uses bilinear interpolation instead of nearest neighbor for the *aspect ratio* and *stretch mode*. It does not affect the graphics mode scaling unless OpenGL is selected, in which case it determines how the OpenGL scaling is done.

Nearest neighbor is a simple way to scale an image; each pixel becomes multiple pixels of the same color. While this preserves the sharper details in a pixel art image, it also creates “jagged” edges as the image is scaled up. Bilinear interpolation finds the average color between pixel color values and fills in missing pixel, which results in a “smoothed” image.

To toggle between bilinear interpolation and nearest neighbor, press Ctrl+Alt+f.



Fig. 16: Maniac Mansion with Hercules Green render mode



Fig. 17: Maniac Mansion with Hercules Amber render mode



Fig. 18: Maniac Mansion with CGA (4 color) render mode



Fig. 19: Maniac Mansion with EGA (16 color) render mode



Fig. 20: Maniac Mansion with Amiga (32 color) render mode

Chapter 35

Report a bug

To report a bug, go to the ScummVM [Issue Tracker](#) and log in with your GitHub account.

Please make sure the bug is reproducible, and still occurs in the latest git/Daily build version. Also check the [compatibility list](#) for that game, to ensure the issue is not already known. Please do not report bugs for games that are not listed as completeable on the [Supported Games](#) wiki page, or on the compatibility list. We already know those games have bugs!

Please include the following information in the bug report:

- ScummVM version (test the latest git/Daily build)
- Bug details, including instructions for how to reproduce the bug. If possible, include log files, screenshots, and any other relevant information.
- Game language
- Game version (for example, talkie or floppy)
- Platform and Compiler (for example, Win32, Linux or FreeBSD)
- An attached saved game, if possible.
- If this bug only occurred recently, include the last version without the bug, and the first version with the bug. That way we can fix it quicker by looking at the changes made.

Finally, please report each issue separately; do not file multiple issues on the same ticket. It is difficult to track the status of each individual bug when they aren't on their own tickets.

35.1 The ScummVM log file

To help you report a bug, you can find error messages in the ScummVM log file. The location of this file varies depending on your operating system.

macOS

`~/Library/Logs/scummvm.log`

Linux

We use the XDG Base Directory Specification, so by default the file will be `~/.cache/scummvm/logs/scummvm.log` but its location might vary depending on the value of the `XDGLCACHE_HOME` environment variable.

Windows

Window Vista/7/8/10

`%APPDATA%\ScummVM\scummvm.log`

Chapter 36

Contact us

There are a few ways to become a part of the ScummVM community:

- Chat with us on [Discord](#) or the [IRC Channel](#) . It's a great place to hang out with developers and other ScummVM users.
- Post on the [ScummVM Forum](#) . We have several forums; the [Help and Support forum](#) if you need help while using ScummVM, the [General discussion forum](#) for all general questions, and [The Junkyard](#) for almost everything else! We also have some platform-specific forums, in case you have a specific question. Make sure to read the [Forum Rules](#) before posting.
- There are three ScummVM mailing lists, which you can join [here](#).
- If you find a bug, [Report a bug](#).
- Feature requests can be made to our [Feature request tracker](#).
- If you have made modifications to the ScummVM source code and would like to see them merged into the main code, open a Pull Request on our [GitHub page](#).

We look forward to meeting you!

Chapter 37

Frequently Asked Questions

Contents

- *Frequently Asked Questions*
 - *General*
 - * *About*
 - *Is ScummVM an emulator?*
 - *Is ScummVM free?*
 - *How do I install ScummVM onto my device?*
 - *How do I get game files onto my device?*
 - *On what platform(s) will ScummVM run?*
 - * *Games*
 - *Can I only play LucasArts SCUMM games?*
 - *Where do I get the games?*
 - *How do I install games from my floppy discs/CDs?*
 - *Do I need the original game discs?*
 - *How do I know if I can play my game using ScummVM?*
 - *I have saved games from when I played the original game - can I use these with ScummVM?*
 - *How do I launch a game straight from the game folder?*
 - *What are the in-game keyboard shortcuts?*
 - *Troubleshooting*
 - * *ScummVM*

- *ScummVM crashes, but the console window disappears too quickly to see the error message.*
- *I think I found a bug. What do I do?*

* *Games*

- *Help! My game won't run!*
- *I installed my game but ScummVM can't find it... What do I do?*
- *Why are the subtitles in my non-English game messed up?*

* *Audio*

- *Help! There's no sound!*
- *Help! There's no sound on my iPhone/iPad!*
- *I have a "talkie" version of a LucasArts game but I can't hear the voices. What's the problem?*
- *The audio is really glitchy. What can I do?*
- *I have a CD version of a game, how do I get the sound to work without running the game from the CD?*

* *Graphics*

- *There are so many options... How do I know what to pick?*
- *Can I just make the image larger (for example, 1 pixel becomes 4 pixels) without any smoothing or antialiasing?*
- *The game colors are messed up, how do I fix them?*

37.1 General

37.1.1 About

Is ScummVM an emulator?

No! ScummVM actually replaces the original executable file that shipped with the game. This means that your games can run on platforms they were never designed for! For an in-depth look at how ScummVM works, see the [About ScummVM](#) wiki page.

Is ScummVM free?

ScummVM is released under the GPL (General Public License), so it's more than just free. ScummVM source code is available for you to do whatever you want with it, but if you make modifications and redistribute your work, you must make your source code available.

The ScummVM team would be delighted if you send them your modifications, so that the changes you've made can be merged into the main source code. See the [Developer Central](#) wiki page for contributing guidelines.

How do I install ScummVM onto my device?

See [Start here!](#).

How do I get game files onto my device?

For general guidance, see the [Handling game files](#) page. For platform-specific information, see the relevant page in the **OTHER PLATFORMS** section of the sidebar.

ScummVM has cloud and LAN functionality to simplify the file transfer process. For more information, see [Connecting a cloud service](#) and [Using the local web server](#).

On what platform(s) will ScummVM run?

See our [Platforms](#) wiki page for a full list. We have guides available for many of the supported platforms, see the relevant page in the **OTHER PLATFORMS** section of the sidebar.

37.1.2 Games

Can I only play LucasArts SCUMM games?

Although the ScummVM project started by reverse-engineering just the LucasArts SCUMM games, the project now supports hundreds of games from many different game developers. See the full list of supported games [here](#). There is a caveat; not all supported games are playable on all platforms. Often this is because the game is simply too CPU intensive for the device, or because of some other hardware or software limitation. If a game is not available on a platform, you will not be able to add it to ScummVM.

Where do I get the games?

See the ScummVM [Where to get the games](#) wiki page.

How do I install games from my floppy discs/CDs?

Generally speaking, you do not need to install the games. You only need to point ScummVM to the game files contained on these discs. For a complete guide, see [Handling game files](#).

Do I need the original game discs?

Ideally yes, however we know that a lot of people don't! If you do not have any hard copy games, there are some digital options available, including some games that have been released as freeware. See the ScummVM [Where to get the games](#) wiki page.

How do I know if I can play my game using ScummVM?

The best place to check is the [Compatibility](#) page on the ScummVM website. You can also have a look at the full list of supported games [here](#).

I have saved games from when I played the original game - can I use these with ScummVM?

This is only supported for a select number of games. See the [wiki](#) page for the game you are playing.

How do I launch a game straight from the game folder?

Games must be added to and started from *the ScummVM Launcher*; they cannot be started directly from the game files. See [Adding and playing a game](#).

What are the in-game keyboard shortcuts?

A list of default shortcuts can be found on the [Keyboard shortcuts](#) page. Since version 2.2.0 you can also create custom shortcuts on the [Keymaps](#) tab.

37.2 Troubleshooting

37.2.1 ScummVM

ScummVM crashes, but the console window disappears too quickly to see the error message.

If you are using a computer, you can run ScummVM from the *command line*. By doing this, error messages remain visible even after ScummVM exits.

You can also find error messages in the ScummVM log file. See *The ScummVM log file*.

I think I found a bug. What do I do?

See *Report a bug*.

37.2.2 Games

Help! My game won't run!

1. Make sure your game is supported. Check the [Compatibility page](#) on the ScummVM website, and the [Platform Overview](#) page on the wiki.
2. Check that you have all the required datafiles. See the *Handling game files* page.
3. Ask for advice on the ScummVM forums or on Discord. See the *Contact us* page.
4. If you think the game should run, and it doesn't, report it as a bug. See *Report a bug*.

I installed my game but ScummVM can't find it... What do I do?

Installing the game does not necessarily provide ScummVM with the files it needs. In most cases you will need to copy the files from the disc into a folder ScummVM can access. See *Handling game files*.

Why are the subtitles in my non-English game messed up?

You need to specify the correct *language* in the game-specific settings.

37.2.3 Audio

Help! There's no sound!

Sometimes it's worth checking the obvious.

1. Are your speakers on? Are your headphones properly connected?
2. Try playing an audio clip from another source to see if you have sound in general.
3. If you narrow it down to an issue with ScummVM, check the [audio settings](#). ScummVM falls back on an audio setting that works, but if for some reason it doesn't, you might need to change the settings yourself. A safe bet is usually to set the **Preferred device** to **<default>** and allow ScummVM to choose for you.

Help! There's no sound on my iPhone/iPad!

ScummVM will not play any sound if your device is in Silent Mode. If this is not the problem, see [Help! There's no sound!](#).

I have a "talkie" version of a LucasArts game but I can't hear the voices. What's the problem?

The original games shipped with an uncompressed voice file (MONSTER.SOU). If you have compressed this file to an mp3 file (MONSTER.S03), an Ogg Vorbis file (MONSTER.SOG), or a FLAC file (MONSTER.SOF), make sure that the ScummVM you're using has support for those formats.

The audio is really glitchy. What can I do?

There are a few things you can try:

- Try to increase the [audio buffer size](#) in the configuration file.
- If you are using the [MT-32 emulator](#), your CPU might not have the processing power to keep up. In this case, you might have some success with running an external MT-32 emulator (Munt), as described in [this forum post](#), provided your platform supports it.
- If you are using [FluidSynth](#), in particular with a large Soundfont, your CPU might not have the processing power to keep up. Try selecting a different [Preferred device](#).
- If you are using the [AdLib](#) emulator, try selecting the least CPU-intensive option; MAME.

I have a CD version of a game, how do I get the sound to work without running the game from the CD?

See *CD audio*.

37.2.4 Graphics

There are so many options... How do I know what to pick?

Start by checking out our *Understanding the graphics settings* page. It has comprehensive information on how all this stuff works.

Can I just make the image larger (for example, 1 pixel becomes 4 pixels) without any smoothing or antialiasing?

Yes. Using the **Normal (no scaling)** graphics mode in conjunction with pixel-perfect scaling will result in a larger image without any smoothing. The **2x** and **3x** graphics modes also do not involve any filtering. Also check that **Filter graphics** is not enabled.

The game colors are messed up, how do I fix them?

Ensure the correct game platform has been detected. For example, with Amiga game files, check that the *platform* is set to Amiga.

Chapter 38

Version 2.2.0 - “Interactive Fantasy”

38.1 New games

Currently, more than 1600 games are detected and supported.

- Added support for Blazing Dragons.
- Added support for Griffon Legend.
- Added support for Interactive Fiction games based on the following engines:
 - ADRIFT (except for version 5)
 - AdvSys
 - AGT
 - Alan 2 & 3
 - Archetype (newly reimplemented for Glk from the original Pascal sources)
 - Hugo
 - JACL
 - Level 9
 - Magnetic Scrolls
 - Quest
 - Scott Adams
 - ZCode (all ZCode games except the Infocom graphical version 6 games).
- Added support for Operation Stealth.
- Added support for Police Quest: SWAT.
- Added support for English translation of Prince and the Coward.
- Added support for Ultima IV - Quest of the Avatar.

- Added support for Ultima VI - The False Prophet.
- Added support for Ultima VIII - Pagan.

38.2 New ports

- MorphOS port got a major rewrite.

38.3 Engines

38.3.1 General

- Autosaves are now supported for all the engines.
- Errors are more likely to open the debugger, and be displayed, than just crash ScummVM.
- Games are sorted in GUI ignoring the articles.
- Now Hebrew is displayed correctly in GUI (requires FriBiDi library).
- Updated the Roland MT-32 emulation code to Munt 2.4.0.
- Added option to select the default voice for ports that support Text-to-Speech.
- Added support for Discord Rich Presence integration on supported platforms (Windows Vista+, macOS 10.9+ 64 Bit)
- Major improvements to the keymapper.

38.3.2 BBVS

- Added support for the demo, available from our website.
- Added support for the Loogie minigame demo.

38.3.3 Dreamweb

- Added support for Russian fan-translation.
- Fixed animation speed.

38.3.4 Illusions

- Fixed subtitle speed (set it to max for good speed).
- Added support for Russian Duckman.

38.3.5 Kyrandia

- Added support for the SegaCD version of Eye of the Beholder I (with CD-Audio, animated cutscenes and map function).
- Added support for the PC-98 version of Eye of the Beholder I.
- Added support for the Spanish versions of Eye of the Beholder I and II, Legend of Kyrandia 1 (CD-ROM fan translation) and Legend of Kyrandia 2 (floppy version and CD-ROM fan translation). Fix Spanish Lands of Lore support (floppy version and CD-ROM fan translation).

38.3.6 Lab

- Fixed sound looping in some rooms.

38.3.7 Neverhood

- Added support for bigger demo, available from our website.

38.3.8 Prince

- Fixed inventory item descriptions display.
- Added English translation.
- Fixed bug with infinite loop when looking at some objects.

38.3.9 Queen

- Fixed loading a save game from the launcher.
- Fixed random long delays when starting a game.

38.3.10 SCI

- Major improvements to Amiga and Mac sound drivers.
- Improved MIDI playback and fixed many audio issues.
- Fixed 30 original script bugs in ECO2, GK1, KQ4, KQ5, KQ6, KQ7, LB1, LONGBOW, PHANT2, QFG1, QFG3, QFG4, SQ5 and SQ6.
- Fixed a script bug responsible for rare and random lockups in most Sierra games between 1992-1996.
- Added support for Inside the Chest / Behind the Developer's Shield.
- Added support for German LSL6-Floppy.
- Added support for Hebrew Torin's Passage.
- Added support for Italian Lighthouse.
- Added support for Polish KQ5, LSL2, LSL3, LSL5 and LSL6-Floppy.
- Fixed Russian LSL1 error when hailing a taxi.
- Fixed Phantasmagoria 2 error when attempting easter eggs.
- Fixed QFG3 auto-saves.
- Fixed QFG4 and Shivers save game thumbnails being obscured by control panels.
- Fixed a random crash in the Windows version when exiting a game.
- Added support for Roland D-110 sound driver.
- The **Prefer digital sound effects** checkbox now works correctly for SCI01/SCI1 games.

38.3.11 SCUMM

- Fixed palette issues leading to incorrect colors in MM NES intro and dark rooms.
- Fixed the rendering of the flashlight in MM NES to match the original version.
- Replaced the existing NES palette to a more accurate NTSC palette based on Mesen.
- Added a new GUI option to switch to an alternative NES palette based on the NES Classic.
- Improved colors in Apple IIGS Maniac Mansion.
- Fixed crash when entering garage in Apple IIGS Maniac Mansion.
- Added support from Classic Full Throttle from Remastered release.

38.3.12 Supernova

- Improved English translation.

38.3.13 Sky

- Fixed syncing of music volume between built-in settings panel and ScummVM configuration.

38.3.14 Sword1

- Added support for localized menus in Novy Disk Russian Trilogy release.
- Added support for Spanish playable Demo available from our website.

38.3.15 Sword2

- Added support for Spanish playable Demo available from our website.

38.3.16 Titanic

- Fixed Barbot crash after asking what else he needs.

38.3.17 Wintermute

- Added subsystem for tracking achievements, implemented for 10+ games.

38.3.18 Xeen

- Added missing sprite drawer for enemies hit by Energy Blast.
- Fixed freeze due to bad mob data at the top of Witches Tower.
- Fixed crash loading some savegames directly from the launcher.
- Fixed curing the well in Nightshadow.
- Fixed loading of wall items from savegames.
- Fixed U/D keys not working on Quests dialog
- Fixed incorrect mirror destination for Dragon Tower
- Fixed crash reading book in Great Pyramid safe
- Prevent attributes from going negative
- Fixed border faces animation during Clairvoyance

38.3.19 ZVision

- Fixed regression in the safe puzzle in Zork Nemesis: The Forbidden Lands.
- Fixed getting perfect score in Zork: Grand Inquisitor.

38.4 Ports

38.4.1 Android port

- Added support for immersive fullscreen mode.
- Improved keyboard and mouse input.

38.4.2 iOS port

- Fixed unsupported graphic mode for some games (such as SCI games with high quality video scaling enabled).
- Removed Quit button to follow the iOS design guidelines.
- Removed virtual keyboard input assistant bar. In particular this means that we no longer see a bar at the bottom of the screen when using an external keyboard.
- Added save of current game state if possible when switching to a different task and restore game state when returning to the ScummVM task.

38.4.3 Linux port

- Added option to use the system file browser instead of the ScummVM file browser.

38.4.4 MacOS X port

- Fixed blurry on Retina screens. Unfortunately this required dropping support for the dark theme for window decorations.
- Fixed Taskbar icon display when running a game (this was broken since ScummVM 1.9.0).

38.4.5 RISC OS port

- Added a VFP optimized build for newer hardware.

38.4.6 Windows port

- Added support for using additional OneCore voices for text to speech.
- Active support for Windows Vista and lower is now discontinued. While we still provide builds for those systems in the foreseeable future, some newer features might be missing.

Chapter 39

Welcome to ScummVM!

ScummVM allows you to play classic graphic point-and-click adventure games, text adventure games, and RPGs, as long as you already have the game data files. ScummVM replaces the executable files shipped with the games, which means you can now play your favorite games on all your favorite devices.

So how did ScummVM get its name? Many of the famous LucasArts adventure games, such as Maniac Mansion and the Monkey Island series, were created using a utility called SCUMM (Script Creation Utility for Maniac Mansion). The ‘VM’ in ScummVM stands for Virtual Machine.

While ScummVM was originally designed to run LucasArts’ SCUMM games, over time support has been added for many other games: see the full list [here](#). Noteworthy titles include Broken Sword, Myst and Blade Runner, although there are countless other hidden gems to explore.

39.1 Start here!

We have a user manual section covering **THE BASICS**:

Installation

Installing ScummVM on a computer

Understanding the interface

Playing games

Handling game files

Adding and playing a game

Saving and loading a game

Controls and settings

Keyboard shortcuts

Changing settings

Useful features

Connecting a cloud service

Using the local web server We also have guides on how to get ScummVM running on a wide range of other platforms:

Handheld consoles

Nintendo 3DS

Nintendo Switch

PlayStation Portable

PlayStation Vita

Other consoles

PlayStation 3

Sega Dreamcast

Phones and tablets

iOS

Android

Other operating systems

AmigaOS 4

Atari/FreeMiNT

RISC OS

39.2 Advanced topics

For our more experienced users, ScummVM features a command line interface, as well as the ability to edit settings directly in a configuration file.

In this section, we also take a deep dive into understanding the graphics and audio settings.

Advanced features

Configuration file

Command line interface

Understanding the settings

The audio settings

The graphics settings

39.3 Getting help

ScummVM is still under development. While we do our best to make sure that as many games as possible can be completed with no major bugs, crashes can happen!

If you are having problems with any aspect of ScummVM, take a look at our help section.

[Frequently Asked Questions](#)

[How to report a bug](#)

[Contact us](#)

39.4 What's changed since I was last here?

We have a **RELEASE NOTES** section on the sidebar; here you can see what's changed in both current and past releases.

39.5 The ScummVM Project

ScummVM is an open-source project created, maintained and constantly improved by a team of passionate volunteers from all around the world. If you enjoy using ScummVM and would like to support the team, you can use the PayPal Donate button below.

Another way to support us is to buy your games from GOG.com using the ScummVM Affiliate link.

If you have software development or technical writing skills, we would love for you to join the ScummVM team! Check out [Developer Central](#) on the ScummVM wiki for more information on contributing to ScummVM.